



User Manual

Copyright © AquaSoft GmbH 1999-2015

Contents

1	First steps	1
1	First steps with AquaSoft® SlideShow	1
2	Program overview	9
3	The Timeline	17
2	Design options in AquaSoft® SlideShow	19
1	16:9 or 4:3?	20
2	Transitions	23
3	Text animations	27
	Text to images	27
	Text without an image	31
	Rotating text	35
	Multiple texts	36
	Letting texts fly	41
4	Multiple tracks	52
5	Ken Burns Effect	60
6	Adding videos	64
7	Collage	66
8	Movement paths	69
	Simple movement shots	70
	Movements with alterations in size	73
	Movement paths with rotations	79
	Text with movement paths	80
	Camera pans	83
9	Zoom	86
10	Rotations	91
11	Image effects	96
12	Animated transparency	98
13	Background music	100
14	Custom volume settings	103
15	Sound objects	103
16	Saving own templates	104
17	Using the SlideShow-Master	108
3	Properties of slideshow objects	110
1	Image	112
2	Text	116
3	Video	117
4	Sound	119
5	Collage	120

6 Chapter	121
7 Particles	121
4 Controlling the slideshow	123
1 Automatic course	123
2 Manual control	123
3 Automatic and manual course mixed	125
4 Repeating the slideshow infinitely	125
5 Export options	126
1 DVD-Player	126
2 PC-Show	132
3 Additional video formats	133
4 Archiving a slideshow	134
5 Additional export options	135
6 Image editing	135
1 Integrated image editing	135
2 AquaSoft® Image effects	136
A simple shadow	138
A "self-border" using multiplication and transformation	140
7 Wizards	142
1 Export Wizard	142
2 ScreenShow Wizard	144
3 SlideShow-Manager	146
4 Sound Wizard	146
5 Import Wizard	149
6 PowerPoint Wizard	149
7 Video Wizard	151
8 CD/DVD- and Archiving Wizard	151
9 Photo Frame Wizard	152
10 PSP Wizard	154
11 iPod Wizard	156
12 Mobile Wizard	158
13 Find missing files	162
8 Variables	163
9 Settings	166
1 View settings	166
2 Slideshow settings	166
3 Music settings	171
4 Program settings	172

10 Technical information	180
1 Common preparations	180
2 Installation	181
3 Full screen mode with different screen resolution	181
11 Ordering AquaSoft ® SlideShow	182
12 Other programs by AquaSoft	182
1 AquaSoft ® Barbecue	182
2 AquaSoft ® DiscMenu	183
3 AquaSoft ® Multimediawerkstatt	184
4 AquaSoft ® PhotoAlbum	185
5 AquaSoft ® PhotoCalendar	186
6 AquaSoft ® ScreenShow	187
7 AquaSoft ® WebShow	188
13 AquaSoft ®	189
1 If you have problems	189


1 First steps

1.1 First steps with AquaSoft® SlideShow

Start the program, then select an empty 4:3 slideshow in the *Welcome dialog*.


Before you start with your work switch to *View -> Layout*. Here you will also find the *Timeline*.

1. Adding images



You can select and add photos via *Add -> Images*. You also can add whole directories via *Add -> Directory*. The selected images will be displayed in the *Timeline*. By using *Edit -> Sort* you can get the images into a certain logical order, e.g. by their *EXIF*-exposure date. Naturally, you can sort your images manually, as well.


2. Adding background music



Music enriches your life and your show. Via **Add -> Background music** you can select music titles by clicking the **Plus**-button. The order of the titles can be changed by moving them with the mouse.

Remove titles from the list by clicking the **Trash bin**-button. If you select a title you can adjust its settings. Then click **OK**. The music titles will be displayed in the **Timeline**.


3. The show can begin



This quick you can see results. In two steps you added pictures and music, and now you can play your show. To do this click the **Play**-button in the menubar or **F9**. Transitions are selected randomly and each time you play the show your images have a different transition.

That's not enough yet? You want to specify the display duration, enter text and define transitions yourself? No problem with **AquaSoft® SlideShow!**

4. Image properties




Select the first image. On the right side you will find the image properties. Here you can assign a fixed transition, text and comments to the image. You can also customize the duration of the image.




If you want to change the duration of several images at once select all images that are to be edited via **Ctrl+A** in the Image list and change the value of the duration. It will be assigned to all selected images. Under Program settings you can also change the default value for the duration. These changes then apply to all images that have **Use default duration** checked.

5. Specifying transitions




If you don't want to leave the transition to chance select the one you want from the list. If you click the **Adjust**-button you can further edit the transition properties.



With the -button (... from here) in the menubar you can play the show from the position of the currently selected image.

6. Text fade-in




Under object settings for images you can find the tab **Text**. Here you can enter text to accompany the image and also add formatting. The text can have an animation applied as well. After clicking the **Edit**-button you can customize this animation and specify whether or not to leave the text in place after playing the image. If you activate the function **Show text with image** the text will be displayed together with the image and will not be animated separately.

8. Ken Burns Effect

7. Commenting images




On tab **Sound** you can record a comment via a connected microphone. To do this click the **Record** -button. The duration of the image will be automatically adjusted to the comment. Alternatively you can assign a specific sound file to the image. Click on the yellow folder to select the file.



SlideShow provides predefined **Movement paths** in the **Toolbox**. Among them you can find the **Ken Burns Effect**. Drag the Ken Burns Effect from the **Toolbox** directly to an image in the **Timeline**. Now play that image. There are many more options to animate images with zooms and camera pans. You can find more information about this at a later point in this manual.

9. Image effects




Just as easy as adding a **Ken Burns Effect** you can assign other special **Image effects**. To do this go to

Image effects in the **Toolbox**. Drag an image effect to an image in the **Timeline**. Click on this image and you will see it in **Layout Designer** with the effect applied.


Image effects influence how an image is displayed. They are not transitions. Those you can find in the image properties (Box 4 on this page) and under **Transitions** in the **Toolbox**.

10. Creating a collage



In the **Toolbox** you can find the **Collage**-object. It allows the display of several images and texts at the same time. Simply drag it from the **Toolbox** to the **Image list** to insert it into the slideshow. Now select those images from the Image list that you wish to include into the collage and drag them to the **Collage**-object. Expand the collage so that the images are displayed. Under object settings for collages you can select the transition you want to apply.

11. Editing a collage



Select the first image in the collage and resize it in **Layout Designer** by using the position frame at the edges of the image. Now position the image. Repeat these steps with all images in the collage. In the Toolbox you can also find the **Text**-object. Select the last image in the collage, then click the **Text**-object to insert it. The text will be added as the last object of the collage. On the **Text**-tab in Object setting you can add and format text. Now position it. Select the collage from the Image list and click the **... from here**-button to play the collage.

12. The powerful chapter



One image track is not enough for you? Then you can utilize the chapter. In contrast to the collage images and text inside a chapter don't lose their own animations and can also be temporally offset. Insert a **Chapter**-object and drag two images into the chapter. Open the chapter by clicking on the **Plus**-symbol, select the last image in the chapter and then double-click the **Text**-object in the **Toolbox** to add text after the image. To create a


new track move the second image in the **Timeline** under the first. A red bar appears, which helps you with the positioning. Now move the **Text** underneath the second image and assign an animation to the **Text** -object via the **Object settings**.

13. Temporal fine tuning



Extend the duration of the first image to 10 seconds. To do this simply drag the right edge of the preview image farther to the right. Then move the second image to the right also using the mouse. Extend the text and move it inside the **Timeline** a few seconds to the right. Select the **Chapter** and click the **... from here** -button. The text appears after the first image has been displayed for a few seconds and will be shown with an animation. In this example the text will also be shown in the second image.

14. Chapters can do even more



Chapters offer a variety of other options. Decrease the size of the second image inside the **Layout Designer**. In **Object settings** deactivate the function **Fill**. Now move the image a little inside the **Timeline**. Play the chapter again using **... from here**. This way you can easily create many different picture-in-picture effects.

15. The chapter on a DVD?

The chapter also serves to divide the show into different parts. It helps to keep the overview in large shows. In addition these chapters can be utilized in a DVD-menu later. (Feature of **SlideShow-Manager**, which is part of **SlideShow Ultimate and Blue Net**.)

After you finished the creation of your show you can create a DVD for the DVD-player. This isn't necessary if you wish to continue to play the show on the PC.

16. Burning

Under **Wizards** you can find the **SlideShow-Manager**. Here you can specify which menu to use to create your DVD. Select a template, then go to **Project -> Burn project**. The **Video-DVD** is for the DVD-player. A self-starting CD/DVD for PC will be created under **PC show**.

If you're using **SlideShow 7 Premium** select **Video Wizard** to create a DVD for DVD-player. The **CD/DVD and Archive Wizard** creates a self-starting CD/DVD for PC.

The conversion of a slideshow into a video can take some time. After that you can put the burned DVD in your DVD-player and start the show.

Now you've created a slideshow with effects and background music. Your family and friends will be impressed.

Naturally, there is much more to discover, and you can now start with experimenting with the **multitude of other possibilities** in **AquaSoft® SlideShow**, like editing images, using zoom functionality, recording comments, burning CDs/DVDs, etc.


1.2 Program overview

Structure of the user interface


AquaSoft® SlideShow includes several tools to edit your show. In the following graphics you get an overview over the available controls. We will talk about objects often. **All** elements that can be added to a slideshow, e.g. images, text, music or collages, are objects.



The description of the controls is given with respect to the **Layout** view. You can select it via **View -> Layout**.



The toolbar



Creates a new empty show.



Opens an existing show.



Saves your show.



Adds images to your show.



Opens the dialog to add background music.



Opens the slideshow settings. The settings only apply to the currently opened show.



Plays your show from the beginning.



Plays your show from the current position.



Opens the Export Wizard.



Allows searching for text, file names and keywords inside your slideshow.



Loads SlideShow's **Layout** view.



Loads SlideShow's **Storyboard** view.




Loads SlideShow's **Image list** view.



Loads SlideShow's **Toolbox** view.

The Layout Designer

The **Layout Designer** is your preview window. Here you can see how images and text will be displayed on the monitor.



The following icons are available in **Layout Designer**:



Zooms into the preview in Layout Designer.



Zooms out of the preview in Layout Designer.




Sets the view/window size back to its normal size



Toggles the raster that objects can be magnetically aligned on

[Zoom](#) and [camera pans](#) can be set in [Layout Designer](#) by defining movement marks. You can find the necessary buttons in the toolbar of the Layout Designer. They will be explained in the respective chapters.

At the bottom edge you can find the navigation controls for replay in [Layout Designer](#).




Replays the slideshow from the beginning.



Replays the slideshow from the selected object.

The navigation bar changes after the start of the replay.




Pauses the replay.



Ends the replay.

If you pause the replay additional navigation options become available.



Continues with the slideshow.



Jumps to the previous object.



Jumps to the previous single picture. This way it is possible to carefully check separate sequences.




Jumps to the next single picture. This way it is possible to carefully check separate sequences.



Jumps to the next object.


There are two distinct areas in Layout Designer - the visible and the invisible area.



The visible area represents your monitor. Everything inside this area will be displayed later on the monitor. The invisible area is outside the visible area. We need it to be able to let text, images and other objects fly into the visible area. It means that movements can already take place outside of the visible area and then continue to move into the visible area. This way you can for instance let text run from left to right over the screen. The magnifier icons can be used to increase or decrease the size of the visible area.

The Object settings


Each *Slideshow object* (image, chapter, collages, ...) has certain properties that will be displayed when you select the object in Image list, Timeline or Storyboard. In the following graphic you see the settings for an image. Objects and their properties will be explained in more detail later in this documentation.




You can specify the duration of your image and its transition, for example. On the **Text**-tab you can add and format text. And on the **Sound**-tab you have the option to assign a special comment or sound to your image.

The Toolbox

The **Toolbox** is the place where you find all the objects that can be added to a slideshow. You can click on them and drag them with held-down mouse button to position in the **Image list**. This process is called drag&drop. By double-clicking an object it will be added at the end of the show.



When you click on the **Transitions**-tab in the Toolbox you find a large selection of pre-defined transition effects. Click on a transition and you will get a small preview of the effect. If you want to assign a transition to an image drag it with held-down mouse button to the image (drag&drop).



The Timeline


The Timeline displays the temporal flow of your slideshow and all its images, texts and musical scores. By using **Chapters** you can create multiple tracks. Images and sounds can be spread over these tracks inside the **Chapter**. You can find it in the **Toolbox** on the tab **Slideshow objects**. [Here](#) you learn how to create multiple tracks.



There are two sliders in the bottom-right corner that allow to change the size of the time display and the height of the objects.

The Storyboard


Here you can switch to the **Storyboard**. It shows a small preview, called thumbnail, of all images in the show. This makes it easier to find a certain image in case your show grew rather large. Here too you can change the order of the images by moving them with the mouse.



Use the slider in the bottom-right corner to specify the size of the thumbnails.

The Image list

All objects of your current slideshow are displayed in the *Image list*. In addition, further useful information about the objects are displayed as well.



Object	Start time	Duration	File Size	File Date	Settings	Track	Keywords	EXIF	File name
1. graybg.jpg	0,0 sec	1,2 sec	23.518	01.05.2008					Data\g...
2. Flash	1,2 sec	2,5 sec							
1. Spicy.jpg	1,2 sec	2,5 sec	41.916	01.05.2008		1			Data\S...
2. black1x1.gif	1,2 sec	0,5 sec	43	01.05.2008		2			Data\b...
3. Flash	3,7 sec	2,5 sec							
1. Peach.jpg	3,7 sec	2,5 sec	49.179	01.05.2008		1			Data\P...
2. black1x1.gif	3,7 sec	0,5 sec	43	01.05.2008		2			Data\b...
4. Flash	6,2 sec	2,5 sec							
1. Horses.jpg	6,2 sec	2,5 sec	34.731	01.05.2008		1			Data\...
2. black1x1.gif	6,2 sec	0,5 sec	43	01.05.2008		2			Data\b...
4. Flash	8,7 sec	2,5 sec							
1. Portrait.jpg	8,7 sec	2,5 sec	24.733	01.05.2008		1			Data\P...
2. black1x1.gif	8,7 sec	0,5 sec	43	01.05.2008		2			Data\b...

Here you can see the start time and duration of the objects. For images there is an entry for file size, file date and file name. Under [Extras -> Program settings -> Image list](#) you can select the columns that you want to be displayed.


A check mark in the **EXIF** column means that the image contains EXIF data (e.g. exposure date, camera model and image resolution). These can be displayed in AquaSoft® SlideShow. More information about this can be found in chapter [variables](#).

Another important column is **Track**. It shows in which track of the [Timeline](#) your object is located. If this entry is empty then your object is in the first track. But you can create multiple tracks inside a chapter, and the column Track informs you about the object's track number. Of course you can also see this in a graphical way inside the [Timeline](#).

You can change the order of the images by moving them with the mouse.







1.3 The Timeline

In the **Timeline** you see the chronological sequence of your show. It informs you when an object will be replayed.





Images, text, collages and videos can have different ways to present them. So can images get camera pans, movement paths, transitions and text. The **Timeline** shows you what kind of animation an object has been assigned.

There are:


-  Transition
-  Text without animation
-  Text with animation
-  Image effect
-  Movement path
-  Camera pan

You can also see the file name and duration in the **Timeline**. The sliders in the bottom-right corner allow you to adjust how much you wish to see.

By clicking the  icon the context menu for the object will open. You can use a right-click on the object instead to achieve the same.




During the replay of a slideshow in *Layout Designer* a blue line in the *Timeline* marks the current replay position.



This line "runs" with the show. You can move it after you paused the show.

You can change additional settings for the *Timeline* under *Extras -> Program settings -> Timeline*.



Here you can specify the snapping behavior and the look of the **Timeline**.

If you want to position an object exactly below another object or at a certain point in time the snapping option can be very helpful.



If you deactivated an image of your show (**Show object** deactivated), it will not be displayed anymore in the Timeline. The Timeline displays only objects that are supposed to be replayed. If you want to reactivate an image you can do this in the Image list or in the Storyboard.

2 Design options in AquaSoft® SlideShow

We recommend to first read the section [First steps with AquaSoft® SlideShow](#) prior to the following tutorials. There you will receive an insight into the basic functions of the program.


In the [Program overview](#) section the working environment of **AquaSoft® SlideShow** is explained to you.

2.1 16:9 or 4:3?

At first you have to specify the aspect ratio you want to create your slideshow in. The aspect ratio defines the ratio between image width and image height.




If you want to show your slideshow on TV later the aspect ratios of 4:3 and 16:9 come in handy. Older CRT-TVs only support the ratio of 4:3, while modern flat-panel TVs support both 4:3 and 16:9.




If your images are in format 4:3 or 3:2 (digital single-lens reflex cameras) select 4:3 as aspect ratio.

If they are in 16:9 format select this format respectively.


In case you want to use the format 16:9 even though your images don't have this format, the images need to be adjusted into the 16:9 format. This is not possible without "cropping" the images a little at the top and bottom. Without this cropping it is technically impossible to display a distortion-free image.



Initial state




Adjusted by
"automatic" cropping




Adjusted by
"automatic" stretching

What do you have to do now?


Insert an image into an empty 16:9 slideshow.




You see the black borders left and right of the image.

Decrease the size of the visible area in Layout Designer by clicking on the  icon. Now increase the size of the image by dragging the handles at the corners of the position frame until the black borders disappear. At last position the desired area of the image in the visible area.


Now it should look similar to the next graphic:



You can save this positioning to a template so that you don't have to repeat this process for every single image. To do this simply drag the image from the [Image list](#) to the [Toolbox](#) and specify a name for the template in the now opening dialog.



After clicking **OK** you can find the template in the **Toolbox** under **Slideshow objects -> Custom objects**.




To add additional images in 16:9 format, simply drag the saved template with pressed mouse button onto the **Timeline** or the **Image list**. The dialog to add images appears. Now select the images you want to add, and they will be inserted with the settings of your custom template.

2.2 Transitions




Each image in **AquaSoft® SlideShow** can get a transition assigned. This can be done by changing the settings in the **Object settings** window, but also via the **Toolbox**.



Add an image to an empty slideshow. To do this use the -button in the menu bar.




You can add several images at once by selecting them in the file selection dialog. Press the **Ctrl**-key and click on the images you want to add.




About the Toolbox

In the **Toolbox** you find the **Transitions**-tab. When you click on a transition you will get a small preview.



Using Drag&Drop (moving with the mouse) you can now assign a transition to an image. Click the transition with the left mouse button and hold it down. Move the transition to the target image in the **Timeline**. Release the button when a red border appears around the image.



Click on the image and then on  to play the image with the transition.


If you would like to assign a **Transition** to several or all images select these images.

All images = **Ctrl + A**


Certain images = **Ctrl + right click** on the image


Select the **Transition** with the left mouse key, then click right and select **Apply**. The **Transition** will be

assigned to all selected images.



You can see the specified transition in the **Object properties** of the image. There you can also change it and even customize it. The following text will give a more extensive description.

If you click on an image in the **Timeline** with the right mouse button or click the  icon a pop-up menu will provide you with the option to select a transition.



About the Object settings


Every object in a slideshow has a set of so called **Object settings**. For example, you can set the **Duration**, specify a **Transition** and enter **Text**. Right now we only want to talk about the **Transition**. [Here](#), you can find more about **Object settings**.

Click on an image in the **Image list** or **Timeline**.




If you don't see **Object settings** in your current view you can open it by right-clicking on the image. Alternatively you can reach the **Object settings** under **View -> Controls**.

The transition is set on the **Image**-tab in the **Object settings**.



In the transition list you can see all pre-defined transitions and select one. Each transition is customizable after clicking on **Adjust**.



If you want to change the transition for several images at once just select these image in the **Image list** and set the desired **Transition** in the **Object settings**. It will be assigned to all selected images.

Via **Ctrl+A** you can select all objects in the image list. With the held down **Ctrl**-key and mouse clicks you can select several single images.

2.3 Text animations

Of course a slideshow should also have text, and it shouldn't be just simply displayed but it should be possible to animate it.


In **AquaSoft® SlideShow** you can enter text to an image or display it on a colored background. Texts also can fly over the image along freely definable movement paths.

2.3.1 Text to images

In the **Object settings** of an image there is a **Text**-tab. The **Object settings** will be displayed when you select an image in the **Image list/Storyboard/Timeline** with a mouse-click.








If you don't see **Object settings** in your current view you can open it with a right-click on the image. Alternatively you can reach the **Object settings** under **View -> Controls**.



Here you can enter text to an image and assign formatting like font, font size and font color.

The available formatting options are almost self-explanatory due to their icons, and you probably know them already from word processing applications.


The **Alignment** has a small peculiarity, however.

-  Positions the text at the lower edge of the screen.
-  The text will be displayed in the center of the screen.
-  Positions the text at the upper edge of the screen.
-  **Detaches the text to be able to customize its position.**
-  The text will be displayed underneath the image. This also applies when the image is scaled smaller.

Enter the desired image caption into the text field. Specify font and font size. If you want colored text you can



change the font color. Select the position of the text. If you want a customized text position click the button under **Alignment**. All changes are immediately visible in **Layout Designer**. In the customized position the text gets its own position frame. This way you can freely place the text anywhere on the screen.




In **AquaSoft® SlideShow** you can decide if you want the text to be separately animated or to be part of the transition effect of the image it accompanies .



If you don't want a separate text animation please activate the option **Show text with image**.

For text that you want to be animated you can choose from a list of pre-defined animations. Click the **Edit** button to adjust the settings for the animation. You can also see a preview of the animation in this dialog.



You can also open this dialog by clicking on an image in the [Image list](#) or [Timeline](#) and then on [Select text animation](#).

Under [Fade out](#) you can specify if you want the text to stay visible until the end of the image duration and to be included into the transition to the next image or if the text fades out at the end of the image. The duration of the animation specifies when the fade-out is to be started.

If you set 3 seconds then the fade-out starts 3 seconds before the end of the image display.




By clicking the -button you can save the text effect settings you just selected. They will then be stored in the [Toolbox](#) under [Text effects](#) and can be reused at any time. Saving text effects is only possible with **AquaSoft SlideShow Ultimate and Blue Net**.

After you finished all the adjustments you can then replay the image together with the text by clicking on



You can find all pre-defined [Text effects](#) in the [Toolbox](#) as well. You can use these simply by Drag&Drop, i.e. by dragging them with pressed mouse button to an image.

Select a [Text effect](#) and you will see a preview of it.



As described above, you can enter and format text on the **Text**-tab in the **Object settings**.


2.3.2 Text without an image

In the **Toolbox** under **Slideshow objects** there is the **Colored background**. With this you can fade in text independently of images. The **Colored background** can even be faded in animated.

To insert it, double-click the **Colored background** or drag the object into the **Image list** or onto the **Timeline** with the mouse button pressed down.



When inserting it with the mouse button pressed down, you can also determine the desired position on the **Timeline** and in the **Image list**. Should you wish to add the **Colored background** between two images, drag the object to the desired place with the mouse. A red line will appear between the two images. Release the mouse key to insert the object at this position. This is also possible in the **Image list**.




The **Colored background** is shown on the **Timeline** as a black image. In the **Image list** it is listed as **black1x1.gif**.

The text can now be entered as with a normal image.

On the **Timeline**, click the object with the right mouse button and select **Select text animation**.



Now the **Select text animation** window opens. There you can enter the desired text and select and edit a corresponding animation.




Under **Fade out** you can determine whether the text should remain visible until the end of the image and should be cross faded with the next image, or whether the text should be faded out prior to the end of the image. In this respect, the duration of the animation determines when the fading out should begin.

Should you set 3 seconds, the fading out is started 3 seconds before the image finishes.



With **OK** your entries are accepted and you can use  to play back the text animation on the screen.


The background is now shown in black. If you wish to have a different color, you can do this in the **Object settings** of the **Colored background**. For that purpose, you have to click the object in the **Image list** or on the **Timeline**. Should the **Object settings** not be shown in the view available to you, you can also retrieve them by right-clicking the object.



By clicking the selected button you can change the background color.

You can also have the colored background faded in animated. Under **Transitions** you can select a cross fading effect.

Under **Text** you can carry out the formatting of the text, as well as change the color of the font.



Should the text not be faded in animated, but together with the colored background, check the **Show text with image** option.



The **Colored background** can also be used to **dim out/fade out** images. Should a black background color be set and a cross fading effect selected, it has the effect on the observer of a fading out of the previous image. In this way you can end a slideshow in style.

2.3.3 Rotating text

Adding texts to images or a colored background has been described in previous chapters. This chapter is about their rotation functionality.




This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.

First add a text to an image. This should look similar to the following graphic in **Layout Designer**.



Please note the **green handle** above the text. You can use it to rotate the text. Click the handle, hold down the mouse button and move the mouse in a rotating motion.




The number next to the green handle shows by how many degrees the text has been rotated.

You can find more information about the use of rotated text in chapter [Letting texts fly](#).

2.3.4 Multiple texts

In **AquaSoft® SlideShow** there is also the possibility of fading in multiple texts either simultaneously or with a time delay.


In the **Toolbox** there is the text object for this purpose.



Fading in multiple texts, in sequence


In this example 3 texts to an image appear, in sequence. The number of possible texts is not limited.

Insert an image. Using the **Toolbox**, now add 3 **Text** objects. You can do this with a double-click or by means of drag-and-drop (dragging with the mouse) into the **Image list** or onto the **Timeline**.




Now select the first **Text** object. In that respect, it does not matter whether you click it in the **Image list** or on the **Timeline**.

In the **Object settings** of the **Text** object, you can now enter your desired text and carry out the formatting. Position the text in the **Layout Designer**.




Select an animation and then call the editing function of the text effect via **Edit**.

So that the text is not faded out again before the next text is shown, the **No fade out** option must be set under **Fade out**.




You can also have the text faded out if it is no longer supposed to be visible when the subsequent text is displayed.

Now repeat the steps with the second and third **Text** object.




Then play back the little show with

In the **Object settings** of the **Text** objects you can change the holding time of the texts.




Showing multiple texts simultaneously


In order to now not show the texts in sequence, but simultaneously, the **Chapter** object is required. Use the little show that you have just created.




Add the **Chapter** object into your show.




The **Chapter** can have several tracks and therefore show the **Slideshow objects** in parallel/simultaneously.



Click on the image on the **Timeline** and drag it with the mouse button pressed down to the **Chapter** object. The **Chapter** is framed in red if you go over it with the mouse. If this red frame appears, "drop" the image.



After that it looks like this on the **Timeline**. You now have to open the **Chapter**. There is a little plus symbol for that.



Now drag the first **Text** object into the **Chapter**. Drag it to underneath the image in the **Chapter**. A red vertical bar will appear if you move the mouse to the correct position.




Now drag the first **Text** object into the **Chapter**. Drag it to underneath the image in the **Chapter**.



If you now drag the **Timeline** to make it larger, it must look like in the illustration.



Now play back the show again with . You will see that the image and the texts are all faded in simultaneously.

Using the **Timeline** you can adapt the timing individually. For this, you can simply drag the **Text** objects with the mouse into the starting position.




When you don't work on a chapter you can close it by clicking the minus symbol.

2.3.5 Letting texts fly


The **Text** objects which you have already become acquainted with in the previous section can also be animated with a movement path. In other words, they can "fly" across the image.

For this purpose, the **Layout Designer** provides the necessary tools.

Insert an **Image** and a **Text** object into your show.



Then click the **Text** in the **Image list** or on the **Timeline**. In the **Layout Designer** the tools for the movement path are now enabled.



This is the icon for switching, in the **Layout Designer**, into the mode for movement paths. There is yet another mode for camera pans and zoom. Since this function is not available with the **Text** object, the icon for the movement path mode is active.




Use this button to insert new **movement marks**. The course of the movement is established on the basis of these marks.



In order to remove **movement marks** that have been set, the latter must be selected in the **Layout Designer** and can then be removed with this button.



In this respect, an additional menu for the **movement marks** is opened. This is explained more precisely later on.




The chronological course of a path is established with timestamps. They thereby determine how quickly the sequence should occur. That is clarified in an example below.




Newly created movement paths can be saved using this button and later conveniently reused. This function is only available in **SlideShow Ultimate and Blue Net**.

Inserting a movement mark



Insert a **movement mark** by clicking  .

Positioning a movement mark




You can now drag the **movement mark** inserted in the **Layout Designer**. For that purpose you have to click in the text area and then drag the latter with the mouse button pressed down.

The orange dot shows you which **movement mark** has been selected.



Now you can replay the show by clicking and watch how the text moves.


Chronological sequence



With **Time mark** you can control the sequence. If you increase the time, the sequence becomes slower. If you reduce the time, the sequence becomes faster.

First increase the **Time mark** of the movement point and then replay the show.


Starting time



If the movement sequence is only supposed to begin after a time delay, you can increase the **Time mark** with the first **movement mark**. For that purpose, click the **movement mark** and then increase the time unit. The subsequent **movement marks** will automatically be adapted.

Inserting additional movement marks

You can insert as many **Movement marks** as you like. The new **movement mark** is always inserted **after** the previously selected mark.




Select the last **movement mark** and with  insert a new mark and position it in the Layout Designer.

Play back the show. You will find that the last part of the movement path elapses faster than the first part. You can control this for the 3rd movement mark via the Time mark.


Hard and soft curves

In the course of movement you can choose between **hard** and **soft** curves. With **Hard curves** the path will run exactly in accordance with the movement marks. With **Soft curves** a round course of movement will take place. You can use both curve types within one path.



Select a movement mark. Using the right mouse button you will get the menu for this movement mark and can change the **Curve type** there.

Change the **Curve type** for all 3 marks.



You will see that the **movement marks** now have a rectangular marking point. Selecting **Soft curves** these points become round.


In order to see the change in the path, play back the show.

Rotating text during movement sequence


In **SlideShow Ultimate** and **Blue Net** you can rotate or swing texts during a movements sequence also.

For this purpose there is a green handle above the **Text field**. More extensive information about the rotation


functionality for **Text** you can find [here](#).



First rotate the text at the first and second movement marks. Rotations through 360 degrees are also possible, to create complete rotation.




Play back the show. You will see that the rotation center is, in this respect, the midpoint of the text box. Should the rotation center be the center of the text, enable the **Rotation around text center** function in the **Text properties**.



Behavior of text along a movement path


There is another option for text moving along a path.







Use it to let text "snuggle up" to the path as text block or even character by character. The text will rotate according to the path direction.


Letting the text fly in from outside

There are two areas in the Layout Designer. Firstly the visible area, and then the invisible area.




-  Enlarges the visible area in the Layout Designer.
-  Reduces the visible area in the Layout Designer.
-  Restores the normal view/window size.

Continue to use the show you just created. Reduce the visible area with  in order to see the invisible area in the **Layout Designer**.



Now select the first movement mark and drag it into the *invisible area*.




Play back the show. The *Text* will now fly into the picture from the outside.

Zoom function for text

Just like rotation, this function is only available in **SlideShow Ultimate and Blue Net**.


Traveling along a movement path *Text* can increase and decrease in size. The smallest size is defined by its specified font size.


Select the 2nd movement mark and increase the size of the *position frame* of the *Text*-field.



Play back the show. The *Text* will now fly into the picture from the outside.

Further options


Via  the context menu for the movement marks can be opened. With a right-click on a selected movement mark, this menu can likewise be opened.



Some options have already been used above. The following further options are available:

 Copy path


A movement path already created can be copied and thus re-used with a slideshow object. If you copy a movement path from a text object, this can also be inserted in the case of an image.

 Insert path


With this option, you re-insert a copied path from the clipboard.

 Position frame ▶

If you want to be sure that the text or the image does not change size in the course of your movement path, you can set the Use the size from the previous one option here.

 Curve type ▶

There are hard and soft curves with a movement path. The course of a movement can thereby be modified.

 Transform path ▶

A movement path can also be mirrored or rotated. You will find the available options under this point.

 Custom entry...


A movement path can also be mirrored or rotated. You will find the available options under this point.

 Select all marks

With this all movement marks can be selected. Thereafter it is possible to drag the movement path as a whole.

Manually editing the path

Manually entering the path enables the movement points to be positioned exactly.




The **Layout Designer** is specified with a size of 1000x1000. The center of the image is therefore 500x500. Here you can directly specify the positions and sizes. You can also change between the individual markers in this window.

2.4 Multiple tracks

In **AquaSoft® SlideShow** at first glance you only see an image and music track on the **Timeline**. This serves to provide a better overview. At positions where you require multiple tracks, the **Chapter** object is used.

With this you can connect as many tracks as you want. In that respect, it is not predetermined which objects can contain a track. Therefore you can place images, music or texts on any track.

You will find the **Chapter** object in the **Toolbox** under **Slideshow objects**.



The **Chapter** can be inserted by double-clicking. You can, however, also drag it to the desired position on the **Timeline** or in the **Image list** with the mouse button pressed down.

Insert a few images and a **Chapter** into an empty show.

The **Chapter** is inserted as an empty container. You will then have to move the desired objects into the chapter. You can do that on the **Timeline** or in the **Image list** or **Storyboard**. Click on an image and then drag

it with the mouse button pressed down to the **Chapter**.

If you go over the **Chapter** with the mouse, the **Chapter** is framed in red on the **Timeline**. Let go of the image there.



The **Chapter** now contains a small **Plus** icon.



This shows that the objects are to be found in this **Chapter**. By clicking the **Plus** icon you can open the **Chapter**.




Underneath the **Image** object a hint regarding a new track is displayed. To add an image to the second track you need to move it to this track.




The **red** bar under the first image determines the starting position of the image. The image is inserted at this point.



The reference to a new track now appears under the second image. You can place as many objects as you wish on each track. In that respect, the **red** bar helps you to insert the objects in the correct position.



You can also insert **Slideshow objects** into a **Chapter** directly from the **Toolbox**. First of all drag a **Text** object onto a new track.



You can change the positions within the **Chapter** by dragging the objects with the mouse. By clicking dragging the beginning and the end of an object, the **Exposure time/Holding time** of an object can be changed.



The objects within a chapter behave in a similar way to a pack of cards. In other words, the object on the lowest track is arranged on top of the other objects. In this example, the text is shown on all 3 images. Should the text stand on the first track, it would be covered up by the images.

Example:

Often we are asked how **Track/Sound** is set for only a few images. The **Background music** should be faded out at this point, but not interrupted.



Insert a few images into an empty show and a **Chapter**.




Then move the images into the **Chapter**. In that respect, the images should all be on one track.




Now drag a **Sound** object from the **Toolbox** onto the 2nd track in the **Chapter** in exactly the same way as the **Text** object was inserted into the **Chapter** above.



You can add **Background music** by clicking the corresponding track in the **Timeline**. Using the **Plus** icon, you can insert the track.




The title is then shown on the **Background music track** of the **Timeline**.




The **Object settings** of the **Sound** object should be displayed in the **Object settings** window. If not, select the **Sound** object on the **Timeline** by clicking it with the mouse.

Should the playback length of the sounds be too long for you, you can reduce it. The relevant settings are marked in **red** in the illustration below.



On the **Timeline** you will now see that the **Sound** fits in with the 5 images exactly. The **Background music** is canceled during this period of time. If you insert yet more images behind the **chapter**, you will see how the **background music track** is continued.



Images, **texts** and **sounds** can be combined in a **chapter** as desired.



The **Chapter** has a **Minus** icon at the top on the left if it is open. You can close it by that means if you are no longer working on this chapter. That increases the clarity in a substantial show.



By utilizing **SlideShow-Manager** you can create a menu for your show where you can jump to these chapters directly. **SlideShow-Manager** is already included in **SlideShow Ultimate and Blue Net**. You can also add it as plug-in to **SlideShow Premium**.


2.5 Ken Burns Effect




You will find an example of the **Ken Burns effect** in the sample slideshows supplied with the software.

In **AquaSoft® SlideShow** you can quite simply apply this effect to your images.

Insert a few images into an empty slideshow. In the **Toolbox** you will find the **Ken Burns effect** under **Movement paths**.



To apply it to an image, simply drag the effect out of the **Toolbox** onto the corresponding image.



If you would like to assign a **Ken Burns effect** to several or all images select these images.


All images = **Ctrl + A**

Certain images = **Ctrl + right click** on the image

Select the **Ken Burns effect** with the left mouse key, then click right and select **Apply**. The **Ken Burns effect** will be assigned to all selected images.



Now select **Alphablending** as **Transition** in the **Image Object settings**. The **Fill** function has to be enabled as well.







Then play back the show with

You notice that the transitions could be a little *smoother*. This can be accomplished by using a *Chapter*. Add a *Chapter* to the show. Move the *Images* into the *Chapter* and arrange the images in a stair shape. The start of an image needs to be moved slightly underneath the end of the previous one.



Then play back the show with

The *Ken Burns effect* is implemented by means of a *Camera pan*. You can also change this individually. For that purpose, you have to change in the *Layout Designer* to the *Camera pan* mode. To do that, click  in the *Layout Designer*.



The movement path is now shown in the *Layout Designer*. How quickly or slowly a movement progresses is determined by means of the time set to the 2nd movement mark. The greater the time, the more slowly the movement is carried out.

In order to change the time and thus the sequence, click the 2nd movement mark in the *Layout Designer*. The movement mark with *0.0 sec* is the first one and therefore the starting position. After you selected the 2nd mark you can change the time set via the image under *Time mark*. A selected movement mark is shown in the *Layout Designer* in orange.


When using a *Ken Burns Effect* only a part of the image section is used at the first movement mark. You will notice the smaller *Position frame*. Only during the *Camera pan* will the full image section become visible. Therefore, the *Position frame* is larger at the second movement mark.

You will find more about movement path in the chapters [Movements](#) and [Zoom](#).


2.6 Adding videos

You can not only use images in **AquaSoft® SlideShow**, but you can also insert videos.


To insert a video, you will find the the *Video* object in the *Toolbox* under *Slideshow objects*.



You can insert it with a double-click or drag the *Video* object with the mouse out of the *Toolbox* onto the *Timeline* or *Storyboard* or into the *Image list*.



In the *Object settings* of the video you now have various setting options. Should the *Object settings* not be shown in the view available to you, you can retrieve them by right-clicking the video on the *Timeline* or in the *Image list*.



Should the full length of the video not be played back, remove the check mark beside **Play back the full length of the video**. You can then determine the playback duration individually.

You can crop the video at the beginning using **Start time**. If you don't want to play the video from the very beginning enter the point of time where you want the video to start. Under **Duration** specify its playing time. This way you select the part of the video to be played.

Should the **video** not be intended to be played back full screen size, it can be freely positioned in the **Layout Designer**. You can also assign a cross fading effect to the video.

The **Fill background** function enables you to see the previous image during playback of the video or cover it up with a colored background.

Under **Sound** you can determine whether the background music is supposed to be faded out during the course of the video being played. Should you have your own audio or spoken commentaries in the video, you should use this function.

Further **Object settings** of the video are explained [here](#).

The **video** can also be animated with a movement path. How that functions exactly you can find out [here](#).

Technical information:

Prerequisite for playing videos is a suitable DirectShow filter. In many cases it already exists on current Windows systems.

SlideShow 7 Blue Net comes with its own DirectShow filters for a variety of video formats (AC3, H.264, MKV,

MOV, MPEG1, MPEG2, MP4, MTS, M2TS, Qt, TS, WebM).

If your video can not be played in SlideShow, it could be due to a lack of DirectShow filters for the video format. Partly they can be installed later. There are different codec and filter packs available for download. Please refer to the notes to the codec package and also visit the website of the provider of this package. The installation of codecs can also affect other programs.


Please visit our FAQ (<http://faq.aquasoft.de/index.php?action=artikel&cat=15&id=22&artlang=de>) for detailed information.

2.7 Collage



In only a few steps, you can create beautiful collages.


Double-click the **Collage** object from the **Toolbox**.




In this way a **Collage** is inserted into your slideshow. Click this **Collage** in the **Image list** or on the **Timeline** and you will see in the **Layout Designer** that the **Collage** is empty at the moment. In order to fill it in, just double-click the **Image** object from the **Toolbox**.




In the dialog which now appears, simply select all images to be used for your **Collage**.

These are inserted into the **Collage**, since they were selected in the **Image list** and on the **Timeline**. If you click  next to the **Collage**, you can view all images in the **Collage**.



Now simply click on the individual images and drag/maximize/minimize them as you please, until you are happy with the result. You can reduce the images using the **positioning framework** in the **Layout Designer**.




Now insert a **Text** from the **Toolbox** and position it as you please.






If the **Text** is not inserted into the **Collage** now, the **Collage** was probably not selected when you inserted the **Text**. Click and simply drag the **Text** onto the **Collage** and release the mouse button. This works in the **Image list**, on the **Timeline** and on the **Storyboard**.



Now you have a finished **Collage**, consisting of your images and a text. The images can also overlap. Likewise you can create an image within image effect by not reducing the size of the first image.

If you select the **Collage** object, you can change **Object settings** of the **collage**. You can determine a **transition** and change the exposure time.



Images and texts within a **Collage** are not independently animated. To achieve this you need the **Chapter** object.

As you can see, putting together a pretty **Collage** is achieved quickly and easily.



As in an **image**, in a **Collage** you can zoom and furnish this with a **camera pan**. Simply try it out. You will find more about movement path in the chapters [Movements](#) and [Zoom](#).

2.8 Movement paths

You already learned about **movement paths** in chapter [Text animations](#).

You can apply **movement paths** to the following **Slideshow objects**:



Insert an **image** which you would like to animate with a **movement path**.

Then click on the **image** in the **Image list** or on the **Timeline**. In the **Layout Designer** the tools for the

movement path are now activated.



This is the icon for switching into the mode for *movement paths* in *Layout Designer*.



Using this icon, switch into the mode for *camera pans* and zoom.




Use this button to insert new *movement marks*. The course of the movement is established on the basis of these points.



To remove *movement marks* that have been set, the latter must be selected in the *Layout Designer* and can then be removed with this button.



You can use this to open a further menu for the *movement marks*.



The chronological course of a path is established with timestamps. You can thereby determine how quickly the sequence should occur. That is clarified in an example below.



Your custom movement paths can be saved and reused. This function is only available in **SlideShow Ultimate and Blue Net**.

2.8.1 Simple movement shots



Your images learn to walk. With a few clicks your images wander over the screen. Simply follow these instructions and you will be quickly and comfortably introduced to the colorful, moving world of **AquaSoft® SlideShow**.



Create a new slideshow and insert an *image*.




Image

Click on the *image* in the *Image list* or on the *Timeline*, so that the *image* is displayed in the *Layout Designer*.





In this example we would like to explain how you can arrange for an image to fly onto the screen from outside.


For that purpose, we have to enlarge the invisible area with




Now move the image into the invisible area.




Now insert a new movement mark with . Then move the newly inserted movement mark into the visible area.



Play back the show. You will see that the image now "flies onto" the screen from the top left-hand corner. Increase the timestamp at the 2nd movement mark and movement becomes slower.

In order to be sure that the image arrives in the center of the screen and also the size of the image is not changed, retrieve the **Custom entry** once via .



Select **Mark 2** and enter 500/500 in the center. Also set the **Size of previous item**, so that the size of the image is not accidentally altered during the path.

The **Custom entry** assumes a system of co-ordinates in which the **Layout Designer** is 1000x1000 units wide. Therefore, in order to center our image, enter 500 at X (the horizontal position of the midpoint) and at Y (the vertical position of the midpoint), i.e. half of the respective total extent. You can also use negative numbers. These then refer to the **invisible area**.


2.8.2 Movements with alterations in size

In the previous example there was no change in the size of the image along the movement path. Now we would like to show you how to change the image size in the process. This way images can grow or shrink.

Images grow


The image with the path set from the previous section also has to be modified slightly.

You should see it like this in the Layout Designer:




Now open **Custom entry** using the icon.

Select the 2nd mark and change the setting under **Size** to **Freely adjustable**.



Then close **Custom entry**. It is possible to also carry out the next step from this menu, however we are choosing the **Layout Designer** directly.

Using the **positioning framework**, reduce the image at the first mark, i.e. the mark which is outside the visible area. Then move the mark closer to the visible area.




Now play back the show and you will see that the image is larger when it is in motion.

You can select a **Transition**, or also **None**, in the **Object settings** of the image.

First of all, position the first mark in the visible area. Then restore the **Layout Designer** to **Normal view** using



Then access **Custom entry**.




First of all set the values shown in the image. In the **Object settings** of the image select a **Transition**. Afterwards play back the effect.


Now the image should fly back to its original position. For this, two additional **movement marks** are required.




Click the 2nd mark in the **Layout Designer** and then insert an additional movement mark with




This mark is required to allow the image to stand still. The image should not become smaller again immediately. In this case a movement mark can be directly laid over a previous mark. To do that, you only have to drag Mark 3 over the top of Mark 2 now.



Then increase the time at the 3rd mark, as given in the image above. Then insert a 4th mark with . You will not recognize this immediately, since it is inserted exactly over the top of the 2nd and 3rd marks.


Retrieve **Custom entry** using .




Now, under **Center** and **Size** set the values which have already been used at the first mark.


If you now play back the show, you will see that the image is enlarged and then reverts to its original place.

Now insert a new image into the show. Click on our image above once more and access the context menu


using . There select **Copy path**. Now mark the newly inserted image and access the context menu

again using  and this time select **Insert path**.


In the **Object settings** of the 2nd image you have to disable the **Fill background** function.




Now we will for once change the positions of the first and last marks. To do that, access the context menu

using  and accept the settings below once.

Mark 1:





Mark 4:



Then play back the show once in its entirety. And how do you like the effect?

In **SlideShow Ultimate and Blue Net** you can use **Rotations**. This is easy to accomplish via **Custom entry**, too.

Open the context menu for an image via  and select the 2nd movement mark. Under **Rotation** set the angle to 360 degrees. Do the same with the 3rd movement mark.



Play back the show.

These *movement paths* can be used on the following *Slideshow objects*:



2.8.3 Movement paths with rotations

Movement paths with automatic rotations can be applied to the following *Slideshow objects*:





Images, Collages and Videos can now be rotated automatically directly at the movement path. This way it is possible to correctly rotate cars or planes according to the direction of their path.



This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.

You can activate this option in the Object settings.




Click the  icon and then **Select all marks**. You can see that the the car gets automatically rotated along the path.


2.8.4 Text with movement paths


Just like images, you can also let text move along movement paths. Please read the chapter [Simple movement shots](#) first to get to know how to set movement marks.

Create a new slideshow  and insert a **Text** object.





Now use  to add several new movement marks. Position them in [Layout Designer](#).




If you replay this small example you will see that the text moves along the path.

In the [Object settings](#) for [Text](#) exists an option to specify the behavior of the text along the path during replay.




This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.



- Text block** The text remains horizontally and moves along the path.
- Separate characters** The characters are separately animated and snuggle up to the path.
- Rotate text block** The whole text gets rotated along the path.
- Rotate characters** The characters move separately along the path and snuggle up to it.

Example: Rotate characters



2.8.5 Camera pans



Create a new slideshow and insert an *image*.





Image

Click on it in the *Image list* or on the *Timeline*, so that the image is shown in the *Layout Designer* and the corresponding tools are enabled.





With camera pans the images must be enlarged beyond the visible area. For that purpose, reduce the display


of the visible area with the  icon.



Now enlarge the image using the *positioning frame* until it looks similar to the image below.




Then, with the , insert a new movement mark and position it to the left of the first movement mark.



Increase the time at the second movement marker, so that the movement is carried out more slowly. Should you not wish to have any **Transition** at the beginning of the movement path, you can set **None** in the **Object settings** of the image.

Then, with the right mouse button, retrieve the context menu at the 2nd movement mark marked. Now, in the latter, select **Position frame/Use size of previous item**. As a result, the size of the second movement mark is automatically adapted to the size of the previous one and can no longer be changed accidentally.



Every image with the setting **Use size of previous item** is marked in the **Layout Designer** with a



Now simply click and enjoy the effect.

2.9 Zoom



With **AquaSoft® SlideShow** you can also zoom into your images. If you want to show a particular section of an image enlarged, you can generate this using the corresponding tools in the [Layout Designer](#). In that respect, you can freely choose the area which you would like to zoom in on.

You can apply [Zoom](#) and [Camera pans](#) to the [Slideshow objects](#) below:



Image



Collage



Video

You might find it useful to skim through the [movements](#) tutorial first since the zoom function is based on the movement path system.

Zooming into an image easily



Create a new slideshow and insert an image.





Image


Click on the image in the [Image list](#) or on the [Timeline](#), so that the image is shown in the [Layout Designer](#) and the corresponding tools are enabled.



Select the icon from the upper edge of the [Layout Designer](#) to enter the [Camera pan mode](#).




Now click the  icon. This inserts a movement mark. A **position frame** is now drawn around this additional mark. Reduce the size of this mark by means of the **position frame** and drag the section to the place which is supposed to be enlarged.



So that the **Transition** does not have a disturbing effect on the **Zoom**, you can set the **Transition** in the **Object settings** of the image to **None** or increase the **Timestamps**.

The 2nd mark is still marked (orange). First of all set the time there at 4 seconds. Then click the first mark in the **Layout Designer** and set the value to 3 seconds or more.



You can see that, by changing the time of the first mark, the subsequent marks also change automatically. In this way the movement set remains unchanged within the path.



The exposure time of an image is increased automatically if the time of the movement path becomes greater than the **Duration** set in the Image **Object settings**.




After clicking you can play back the zoom effect.

Motion in the image

If you would like to zoom in on several sections of an image, you can now use a movement path in the image. Imagine you have a group photo and now wish to zoom in on the individual persons. However, you do not wish to constantly zoom in and out, but go over the faces in the image.



For that purpose, you can now insert an additional movement mark with the icon. Position the mark at the desired final point.





If you now play back the effect, you will now see that a camera pan is possible within the image. Using the time of the last movement mark you can control the speed. If you increase the time, the shot becomes slower.


Zooming out

You can have the image cross faded while you are zoomed in on the section, or first revert back to the overall image size.


In order to revert back to the full size, insert a new movement mark. Please ensure that the last movement mark is selected.



The easiest thing to do is now to use the **Custom entry**. Retrieve this with a right mouse-click button or by using the  icon.



At **Mark 4** set 500/500 as the **Center** and 1000/1000 under **Size** . As a result, the image at Mark 4 is displayed in its entirety, again.



Now simply click and enjoy the effect.



If you would like to leave the image at the end exposed a bit longer, increase the **Exposure time** of the image from the **Object settings**. After the end of the movement path, the image then continues to remain on the screen.



When aligning the movement marks, it may occur to you that they snap magnetically to other movement marks and to horizontal and vertical lines of other movement marks. You can prevent them snapping this way by holding down the **Ctrl**-key on the keyboard when moving the mark.

Furthermore, the movement marks are also aligned to the grid which can be enabled using the




icon.

As you can see, it is very easy to zoom images. Simply insert movement marks and position them as desired – and already motions enters your image.



The movement path can be changed using the **Curve type**. Select **Select all marks** by means of the icon and click in the Layout Designer with the right mouse button.

In the context menu which now appears, select **Curve type -> Hard**.



You will now see the change in the form of the movement mark. This is now square, in order to represent the chosen **Curve type**.



After clicking you can see the change in the zoom. The pan in the curves is now **Hard** and is no longer carried out soft.

2.10 Rotations



Just camera pans are not enough for you? You want more zest in your slideshow? Add **freely definable** rotations to your images.



This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.

The following objects can be rotated:



Image



Text



Particle



Collage



Video

It doesn't hurt to read the tutorial [Movements](#) first because the rotations are combined with movement paths. The chapters [Rotating text](#) and [Letting texts fly](#) give more information about rotating text.





Create a new slideshow and add an image.




Image



Select the image in [Image list](#) or [Timeline](#) to display it in [Layout Designer](#). Use the  button in [Layout Designer](#) to zoom out a little.




Now you can use the green handle to rotate the image. Click it, hold the mouse button down and define the rotation angle. Use the [Position frame](#) around the image to decrease its size.



The black area in **Layout Designer** is the visible area. Images need to be positioned in this area if you want them to be displayed. You need the outside area for special purposes like e.g. images or texts that "fly" in from the outside.

To manually specify the rotation angle click on the image in **Layout Designer** and select **Custom entry**.





Now enter the **Angle** under **Rotation**.

Beautify your **Collages** by rotating the images in the **Collage**. **Texts** can be rotated this way, as well.

Of course this is not all you can accomplish with the rotation functionality. Would you like to trace your travel route with a car on a map? Then you can learn how to combine movement marks with rotations.



In our example we let the car follow a road. First we add the image of the road using the  button. Instead you can add your image of the map.




Now we need the car. Preferably it should be a PNG graphic with alpha channel.




Please consult the [FAQ](#) about how to create this type of graphic.


Add the car.



Decrease the size of the image using the *Position frame*.



Now you can start the tour. Add a movement mark and rotate the car a little, following the direction of the road.



Add more movement marks and rotate the car accordingly.




You can adjust the time marks for each movement mark individually. Click on a mark, it will then be highlighted. Change the time mark in the menu bar above the image.



Now replay your show via .

Eventually the complete movement path should look similar to the following graphic.




The **rotation angle** can be larger than 360 degrees. This way you can simulate effects like the skidding of a car out of a curve.

2.11 Image effects

With **AquaSoft® SlideShow** you can now also apply image effects to your images and in this way present your images even more impressively.

In the **Toolbox** you will find the Image effects.



The **image effects** are subdivided into various categories. With the **plus** icon you can open up the individual categories.





Image effects can be applied to an image very easily. Insert a few images into an empty slideshow.

In order to now being able to apply the **image effects** to these images, simply drag the desired effect out of the **Toolbox** to the image in the **Timeline**.



You will see the change in the **Layout Designer**. The effect becomes properly visible when playing back.

If you would like to assign an **image effect** to several or all images select these images.


All images = **Ctrl + A**

Certain images = **Ctrl + right click** on the image

Select the **image effect** with the left mouse key, then click right and select **Apply**. The **image effect** will be assigned to all selected images.



If you want to remove an *Image effect* again, in the category *Common* you will find the *Delete all image effects* object in the *Image effects*.



Simply drag the latter from the *Toolbox* onto the image on the *Timeline* in the case of which you wish to remove an effect set.

In **AquaSoft® SlideShow Ultimate and Blue Net** you can create and edit such effects yourself. A special Dort gibt es einen speziellen *Effect editor* is available. It is explained in chapter [Image editing](#).

2.12 Animated transparency


In **AquaSoft® SlideShow** a transparency behaviour can be assigned to some *Slideshow objects*. This creates impressive effects. For instance, it is possible to let an image or text slowly appear from a black background and later disappear in it.

In this way images and texts can also appear semi-transparent on a previous image.





You can apply the *animated transparency* to the *Slideshow objects* below:




You will find the corresponding possibility for setting them in the *Object settings* of the respective *Slideshow objects*.



Now with the left mouse button set markers in this system, which then form a transparency curve. On the left-hand side you will find the value of the transparency (in %); at 100% transparency the image is completely transparent (i.e. no longer recognizable), at 0% it can be seen completely. Above the curve you will find icons, the meaning of which is:

-  Points are round, the course of the transparency animation is soft.
-  Points are square, the course of the transparency animation is hard.
-  If you have clicked a transparency marker (appears orange), you can delete the marker by clicking the icon.
-  If you have changed the exposure time of the image or text, you can, by clicking this button, have the transparency set adjusted to the exposure time.

Move the markers by clicking an existing marker and keeping the mouse button pressed down. Now simply move the marker to the desired spot and release the button again. In order to delete the animated transparency entirely, you will have to remove all transparency markers.



2.13 Background music

A perfect slideshow not only includes impressive effects, but also background music. The *Timeline* provides its own sound track for *Background music*.


Click here to add background music.
Note: the music track remains empty as long as the slideshow doesn't contain any images

Click this sound track and the *Background music* menu is opened.



By means of the plus icon you can insert music onto that menu.

If you click the song, you can make further adjustments.



You can insert one or also multiple tracks. These are then listed below one another in the list. You can change the sequence by clicking the track and moving it in the list with the mouse button pressed down.



Removes a selected track from the list



Plays back a selected song



Opens the music settings

Fade-in song 0.0 sec

A track can be gently faded in. In this case state how many second the fading in should last until the full volume should be achieved.

Fade-out song 0.0 sec

Songs can also be gently faded out. In other words, they are getting more and more quiet prior to the end. Here set the time, how long prior to the end the fading out should start.

Volume 100 %

Specify here at what volume the track should be played back.

Start song after 0.0 sec

You can delay the start of a track. Specify here the length of the delay.

Start next song after 1.0 sec

If you do not want the following track to begin immediately, specify here the length of the break between songs.

Start position 0.0 sec

It is also possible to only play a section of a track. Here you determine from what point in the song playing should start. For

example, 20 secs -> The song begins at the 20th second. The first 20 seconds of the song are not played.

0 -> From the beginning.



Here you can determine when the song should end. In that respect, the timestamp in the song is to be selected again. If you want to end the song after 2 minutes, enter 120 secs here.

Example: Starting and final positions

You wish to only play 1 minute of the song. However, the part of the song which you would like to play back begins at the 45th second.

Starting position = 45 secs

Final position = 105 secs

You will see the music in its own track in the [Timeline](#). The sound wave display will have alternating colors to make it easier to see when a title starts and ends.




The volume of the background music can be set individually. In the [next chapter](#) you will learn how this is done.



Only use unencrypted music tracks for your slideshows. For legal reasons, **AquaSoft @ SlideShow** does not support the use of music tracks which have been encrypted by DRM or similar procedures.

2.14 Custom volume settings

For each title, no matter if it's *Background music* or a *Sound* object, you can separately adjust the volume. This happens in the *Timeline*.




To get the line, click the wave form of the title. Each click creates a mark that can be moved to adjust the volume. A right-click on such a mark will delete it. The line will be removed when the last mark was deleted.



Background music will be automatically faded-out when a Sound object starts. You don't need to do this manually. You can configure the fade-out volume and duration in the [music settings](#).

2.15 Sound objects

If you have undertaken the desired adjustments with an object/image, you can drag it out of the *Image list* or *Timeline* to the *Toolbox*. A window then opens for saving the template. Enter a name there.



Afterwards you will find the template in the *Toolbox* under *Slideshow objects -> Custom objects*. Click the

object and then select the images. These are then inserted with the desired template.

The **Sound**-object is usually used if a sound will only be played over the length of a certain number of images. This is accomplished by using a **Chapter**. You can find an example in chapter [Multiple tracks](#).

[Here](#) you can find a chapter about **Sound**-properties.




Only use unencrypted music tracks for your slideshows. For legal reasons, **AquaSoft ® SlideShow** does not support the use of music tracks which have been encrypted by DRM or similar procedures.

2.16 Saving own templates

After you got a bit familiar with **AquaSoft ® SlideShow** there is a multitude of options for own objects waiting for you. The goal is to reuse nicely designed compositions and thus saving of time. The principal is simple. You know the different kinds of objects by now. Together with your comments and settings whole slideshows or parts of them came into existence. Some parts are usable only for the slideshow they belong to, in others there are elements that are commonly usable or at least a few times. If you created such elements you can easily save them as new objects.

If you have applied the desired adjustments to an object/image, you can drag it out of the **Image list** or **Timeline** to the **Toolbox**. A window then opens for saving the template. Enter a name there.




Afterwards you will find the template in the **Toolbox** under **Slideshow objects -> Custom objects**. Click the object and then select the images. These are then inserted with the desired template.




Saving own text effects




This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.


If you made changes to a text effect and would like to save them, just click on the  icon.



A dialog opens that lets you save the template.



After the **Text effect** was saved it will be added as a **Custom text effect** to the **Toolbox** and can now be applied to other text/images.




Saving own movement paths



This feature is only available in AquaSoft® SlideShow Ultimate and Blue Net.


Movement paths can be saved, as well. Click on the  icon in **Layout Designer**.



A dialog opens that lets you save the template.



After the **Movement path** was saved it will be added as a **Custom movement path** to the **Toolbox** and can now be applied to other images.



2.17 Using the SlideShow-Master



The **SlideShow-Master** contains a series of slideshow templates which make it easy for you to create a slideshow.

At lightning speed you can select images and music to create an attractive slideshow in connection with a style.

Under **File -> New -> Use SlideShow-Master** you can access the **SlideShow-Master**.




Click **Next** to begin designing the slideshow.

In the next step please insert images using the **Plus** icon.



Then click **Next**.

Now insert your desired background music using the **Plus** icon.



If you don't want to adjust the duration of the slideshow to that of the background music uncheck this option. With this option enabled the duration of the images will be adjusted to the duration of the music.

Next click **Next**.


Now select a style template.



With the **Start preview** button you can inspect the style template.



With some templates you can enter a film title and further personal details. For that purpose, simply click the personalization data directly and enter your desired text.



Next click **Next**.

Now you can decide what the next step should be.



Edit slideshow:

Opens the style template with the images in **AquaSoft® SlideShow** for editing. It is now possible to make individual adjustments.

PC DiaShow auf CD brennen:

This option opens the [CD Wizard](#) and you can record the show on a CD or prepare it for passing on. The CD recorded can then be reproduced on a PC (not on a DVD player).

Video auf VCD, SVCD oder DVD brennen:

This option opens the [Video Wizard](#). With this the slideshow is recorded on a video CD or DVD. First the show must be converted into a video.

3 Properties of slideshow objects

As you have already learnt in the previous sections, there are so-called **Object settings** for the **Slideshow objects**. In these you can configure specific settings for the respective objects.

You will find the **Slideshow objects** in the **Toolbox**.

The **Object settings** can be shown fixed on the user interface (always embedded) or also only displayed when required. If you do not show them on the user interface, you can access the **Object settings** at any time by **right-clicking** the relevant object.

The following fundamental properties are available with every object:

<input checked="" type="checkbox"/> Show object	Determines whether the object should be shown when playing back the slideshow.
Duration: 5,00 sec	Here you can set the exposure time. In other words, how long, for example, an image, text or video is supposed to be shown. The cross fading effects take place within this exposure time.
<input checked="" type="checkbox"/> Use default duration (Settings)	In the Slideshow settings you can set a standard exposure time for your Slideshow objects . If you change the exposure time there, this applies to all Slideshow objects in the show in the case of which the standard exposure time was enabled and to Slideshow objects which are newly inserted.
<input checked="" type="checkbox"/> Leave in place after replay	Normally an image or text is cross faded by a subsequent image. In that respect, the image lingers. If it is not desired in the case of a particular animation, the lingering can also be turned off.




If you deactivated an image of your show (**Show object** deactivated), it will not be displayed anymore in the Timeline. The Timeline displays only objects that are supposed to be replayed. If you want to reactivate an image you can do this in the Image list or in the Storyboard.

3.1 Image

In the *Object settings* of an *Image* you can configure the following settings:

Image



Rotates the image counterclockwise.



Rotates the image clockwise.



Opens the Image editor.



Specifies a movement path.




Specifies a camera pan.

File name	Shows the path and file name of your image.
Aspect ratio	Images have an aspect ratio which is comprised of the height and






	<p>width of the image. If an image differs from the aspect ratio of the slideshow set, it can be decided here how the image should be represented.</p> <p>Keep: The image retains borders when being played back.</p> <p>Crop: Parts are cropped from the edge of the image until the image fits into the correct aspect ratio without edges emerging.</p> <p>Distort: The image is inserted into the aspect ratio of the slideshow, whereby a distortion of the image takes place.</p>
Alignment	Determines the position of the image on the screen.
Rotate in direction of movement	If you assigned a movement path to an image you can let the image automatically rotate along the path. This function is only available in AquaSoft® SlideShow Ultimate and Blue Net .
Fill background	<p>On = Background gets a color filling when display size of the image is reduced.</p> <p>Off = Background doesn't get a filling and the previous object "looks through". For images inside collages or Picture-in-Picture effects it has to be Off.</p> <p>Automatic = The slideshow sets filling to On automatically for images/videos/collages in the first track. If you move an object to the second or a lower track filling will be set to Off. This way Picture-in-Picture effects can be created quickly. If you want to the value to remain select it from the drop-down box.</p>
Transition	Here the Transition can be set or also deselected. For that purpose, in the drop-down list there is None as the first option. With the Adjust button, the transitions can be configured. You can also obtain a preview of all transitions there.

Text



The possible formats are almost always self-explanatory through the icons and you are no doubt familiar with them already from other text programs.

The **Alignment**, however, has a minor peculiarity.

-  Positions the text at the lower edge of the screen.
-  The text is shown in the center of the screen.
-  Positions the text at the upper edge of the screen.
-  **Places the text freely in order to determine the position in the image individually.**
-  The text is shown underneath the image. That also applies if the image is shown reduced in size.

If you **don't** wish to have separate text animation, activate the option **Show text with image**.

Should the text be shown animated, you can select various ready-made animations from the list. You can still adjust the animation using the **Edit** button. You can also see a preview of the animations there.

Rotation around text center refers to animations in which the text is rotated. Under **Edit** you can also determine a different rotation center.

With Behavior along a movement path you can specify how text gets displayed when it moves along a [movement path](#). You can choose if the whole text shall move as a block or even as separate characters along a movement path. In the latter case the characters "snuggle up" to the path.

Sound




<i>Folder icon</i>	Using the yellow folder you can assign commentaries or pieces of music already included to an image.
<i>Play icon</i>	Plays back the music file assigned to.
<i>Record</i>	Opens the <i>Sound Wizard</i> and you can then record a commentary to go with the image.
<i>Volume</i>	Determines the volume of the sound when played back.
<i>Fade background music</i>	You can determine whether the volume of the background music should be faded/decreased when playing back the sound.
<i>Adjust display duration to sound duration</i>	Plays back the sound in its entirety and thereby adapts the exposure time of the image to the length of the sound.
<i>Continue sound after end of image</i>	With this option the image can have a shorter duration than the sound. The sound then simply continues to be played on into the next images until it has come to an end.
<i>Fade-out sound after end of image</i>	Should the exposure time of the image have come to an end, but the sound be longer, with this option the sound is faded out at the end of the image. Under Duration you can set the fading out time.

Transparency

Animated transparency is described in the design options under [Animated transparency](#).

3.2 Text

In the *Object settings* of a *Text* object you can configure the following settings:



The *Text Object settings* do not differ from the *Text Object settings* for images. In this case only the *Show text with image* option is not available. The *Text* object is an independent *Slideshow object*, nonetheless, it can be faded into images and videos.


If you want your text to be moving along a movement path, please have a look at chapter [Text with movement paths](#).

Transparency

Animated transparency is described in the design options under [Animated transparency](#).

3.3 Video

With the *Video object* you can configure the following settings in the *Object settings*:



Video

File name

Shows you the path and file name of your video. Using the yellow folder you can also exchange the video for another video file.

Duration

If you have once changed the playback time of the video, you can set the correct video length again with a click on the time.

Start time

Here you can specify from which position a video is to be replayed. If you don't want to show the first ten seconds enter 11.

Play back video entirely

If the option is selected, the full length of the video is played back. If you deselect the option, you can set the playback duration individually.

Aspect ratio

Videos, just like images, have an aspect ratio, which consists of width and height of the frames. If a video differs from the aspect ration of the slideshow you can here decide how to display the video.

Keep: The video retains borders when being played back.

Crop: Parts are cropped from the edge of the video until the video fits

into the correct aspect ratio without edges emerging.

Distort: The video is inserted into the aspect ratio of the slideshow, whereby a distortion of the image takes place.

Alignment

Determines where the video is supposed to be positioned on the screen.

Rotate in direction of movement

If you assigned a [movement path](#) to a video you can let the video automatically rotate along the path. This function is only available in **AquaSoft® SlideShow Ultimate and Blue Net**.

Fill

On = Background gets a color filling when display size of the video is reduced.

Off = Background doesn't get a filling and the previous object "looks through". For images inside collages or Picture-in-Picture effects it has to be **Off**.

Automatic = The slideshow sets filling to **On** automatically for images/videos/collages in the first track. If you move an object to the second or a lower track filling will be set to **Off**. This way **Picture-in-Picture** effects can be created quickly. If you want to the value to remain select it from the drop-down box.

Transition

Here the **Transition** can be set or also deselected. For that purpose, in the drop-down list there is **None** as the first option. With the **Adjust** button, the transitions can be configured. You can also obtain a preview of all transitions there.

Sound




Here you can determine if the background music should be faded out when the video is played back. If the video does not have its own sound, but perhaps a noise has been recorded, set the volume of the video to 0% and remove the check mark beside **Fade background music**.

Transparency

Animated transparency is described in the design options under [Animated transparency](#).

3.4 Sound


With a **Sound** object the following settings are possible:



With the folder icon you can insert or remove a music file. The track selected is shown on the left next to the icon.



Plays back the music file



Opens the **Sound Wizard**. With this you can record a commentary for the image via a microphone connected to the PC. You can find more on the **Sound Wizard** [here](#).

Volume

Displays the volume at which the sound is supposed to be played back.

Fade out background music

If this option is enabled, the background music is faded (volume decreased) when the music file is played back.

Play back the full length of the sound

If this check mark is selected, it means that it plays back the full length of the **Sound** object.

Continue to play the sound after the duration set

With this option the sound can receive a shorter exposure time. The sound is then simply played on into the next images until it has come to an end.

Fade out the sound after the duration set

Should you wish to only play back the sound for a certain period of time and then end it, you have to select this option. Under **Duration**

you can set the fading out time.


The volume of a sound object can be controlled individually. You will learn more about this in chapter [Custom volume settings](#) .



Only use unencrypted music tracks for your slideshows. For legal reasons, **AquaSoft® SlideShow** does **not** support the use of music tracks that are encrypted with DRM or similar methods.

3.5 Collage

With **Collage** objects you have the following possibilities for settings:



Image

Title	Here you can enter the title for the collage. It serves for a better overview in large slideshows.
Aspect ratio	Images have an aspect ratio which is comprised of the height and width of the image. If a created collage differs from the aspect ration of the slideshow you can here decide how to display the collage.

	<p>Keep: The collage retains borders when being played back.</p> <p>Crop: Parts are cropped from the edge of the collage until the collage fits into the correct aspect ratio without edges emerging.</p> <p>Distort: The collage is inserted into the aspect ratio of the slideshow, whereby a distortion of the image takes place.</p>
Alignment	Determines the position of the Collage on the screen.
Rotate in direction of movement	If you assigned a movement path to a collage you can let the collage automatically rotate along the path. This function is only available in AquaSoft® SlideShow Ultimate and Blue Net .
Fill background	<p>On = Background gets a color filling when display size of the collage is reduced.</p> <p>Off = Background doesn't get a filling and the previous object "looks through". For images inside collages or Picture-in-Picture effects it has to be Off.</p> <p>Automatic = The slideshow sets filling to On automatically for images/videos/collages in the first track. If you move an object to the second or a lower track filling will be set to Off. This way Picture-in-Picture effects can be created quickly. If you want to the value to remain select it from the drop-down box.</p>
Transition	Here the Transition can be set or also deselected. For that purpose, in the drop-down list there is None as the first option. With the Adjust button, the transitions can be configured. You can also obtain a preview of all transitions there.

Transparency

Animated transparency is described in the design options under [Animated transparency](#).

3.6 Chapter

In the **Object settings** of the **Chapter** only a section name can be specified. This serves to provide a better subdivision of your show. This chapter name will be loaded into **SlideShow-Manager** later, provided it is installed. The chapters can thus later be selected individually in a CD/DVD menu and played back.


3.7 Particles

The **Particle** object shows your images in a minimized form and moves them on the screen.



This feature is only available from <%PRODUCERPROGRAMNAME_R_ORIG%> Premium.


In the **Object settings** of the **Particle** object you can adapt the representation to your wishes.



Inserts additional images into the **Particle** object.




Removes selected images from the **Particle** object.




Under Direction you can set in which direction the particles disappear.

Directions:

0 degrees = the particles move out of the image towards the right
 90 degrees = the particles move out of the image towards the bottom
 180 degrees = the particles move out of the image towards the left
 270 degrees = the particles move out of the image towards the top



You set the pace of the movement under speed. The higher the value is, the faster the particles fly over the screen. A value of 0 means no speed. The particles won't move.



Here you determine the size of the particles. The size will be calculated based on the size of the **Position frame** in **Layout Designer**. If the **Position frame** takes up the full in **Layout Designer** and **Particle size** is set to 10% then the **Particles** will be 10% of the size of the **Position frame**. If you reduce the size of the latter the **Particles** become smaller, accordingly.

Number of particles:

With the number of particles, you set the quantity of particles shown.

Movement:

Here you can select an animation for the particles.

Strength of movement: Unit

Here you set how strongly the movement should be carried out. The higher the number, the stronger.

Frequency of movement: Unit

The frequency specifies how often the movement is carried out. The smaller the number, the lower the number of movements.

The **Particle** object can in addition also be provided with [movement paths](#). In **AquaSoft® SlideShow Ultimate and Blue Net** you can even [rotate](#) the **Particle** object.

4 Controlling the slideshow

4.1 Automatic course

It is standard for the images in a slideshow to be automatically played back in sequence. In that respect, you determine in the **Object settings** of the **Slideshow objects** how long an **image**, **text** or **collage** is shown and when to switch to the next object.

No special settings are necessary to accomplish this with **AquaSoft® SlideShow**.


4.2 Manual control

Should you wish to move on manually during the show, you can configure the **SlideShow Player** accordingly in the **SlideShow settings**.


The **SlideShow settings** always refer to the current show open.



From the menu bar you can open the **SlideShow settings** using the  icon. Alternatively you can also open the dialog using **Slideshow -> SlideShow settings**.



Via the **Basic settings** you can access the **Player configuration** directly.




The **Start paused** option switches the show over to being continued manually. You can then continue the show using the cursor and scrolling keys.

If you activate **Forward/back per mouse click** in the dialog, you can continue your show by clicking the mouse.

4.3 Automatic and manual course mixed

With **AquaSoft® SlideShow** it is likewise possible to continue parts of the slideshow manually and let other parts play back automatically. You can alter this as you please.

In the **Toolbox** you will find two **Slideshow objects** for this purpose:



These two objects make it possible to switch between continuing the show manually and letting it run automatically. By double-clicking or by drag-and-drop you can insert the objects into your show.

If you, for example, insert the **Pause** object behind the 3rd image, the show will stop before the 4th image and wait for you to continue using the keyboard or mouse.

The manual replay can be interrupted again with a **Play** object. For that purpose, insert the **Play** object at the point where the automatic course is desired.

Artificial pause:

You can also insert a **Play** object directly behind a **Pause** object. Thus, the show will be stopped at the image before the **Pause** object and, as soon as you continue, the show continues to run automatically.

You can also use the **Space bar** to pause the show during replay. When you hit the **Space bar** again the show continues.




If you convert your show into a video DVD, this function of the two objects is lost. To pause a video DVD, you have to use the pause key on the remote control.

4.4 Repeating the slideshow infinitely



From the menu bar you can open the **Slideshow settings** using the **Slideshow settings** icon. Alternatively, you can also open the dialog via **Slideshow -> Slideshow settings**. Under **End of slideshow** you can enable the **Repeat current slideshow** function.



If you convert your show into a Video-DVD this functionality will be lost. If you create your Video-DVD with **SlideShow-Manager** you can there activate the repetition of the of replay.


5 Export options

5.1 DVD-Player

For the DVD player your show must be converted into a video and then burned as a video DVD. This function is provided by the [Video Wizard](#) and by [SlideShow-Manager](#). [SlideShow-Manager](#) can even burn multiple shows on one DVD that can then be selected in from menu.

Video Wizard

With the Video Wizard you can quite easily burn your show onto a DVD and thus play it back on the DVD player. Under [Wizards](#) you can open the [Video Wizard](#).



Premium and Ultimate



Blue Net

DVD

Creates an MPEG 2 video and burns it onto a DVD as a video DVD.
Resolution: 720x576


SVCD

Creates an MPEG 2 video and burns it onto a CD as an SVCD.
Resolution: 480x576

VCD

Creates an MPEG 1 video and burns it onto a CD as a VCD.
Resolution: 352x288

Select the **DVD** option. Only use **VCD** or **SVCD** if you have a CD burner and no DVD burner. In this case we recommend SVCD. It has a higher resolution than a VCD and thus thus result on a TV is better. Then click **Next**.



Premium and Ultimate



Blue Net

In the settings dialog you can set various options. The **TV border correction** is required if the television frame covers up the visible area at the edge. E.g., the first character could be missing or be displayed incompletely from text that starts directly at the edge. Or the top or bottom of the characters could be chopped off. These settings depend on the TV and manufacturer.


The **Video standard** is automatically set to PAL, the European video standard. NTSC can also be set if you need the American video standard. The aspect ratio is automatically adjusted to the aspect ratio of your slideshow. If you have created a 16:9 show, **PAL (16:9)** is automatically set. With a 4:3 slideshow **PAL (4:3)** is selected. A 4:3 slideshow can not simply be burned as 16:9 show, and vice versa.

Before the DVD can be burned, it must first be converted into a video. An *.mpg-file is created in the process. This needs to be saved to the hard disk prior to the burning process. You can decide the storage location and the name under **Video file**. You can also choose to activate the option to delete the video file after the burning.

Then click **Next** and **Create video**. The process of the video creation can require some time.

If you want to burn more than one CD/DVD with your show you don't need to repeat the process of the video creation for each one of them.

You can access the **Burn video on CD/DVD** option in the **Video Wizard**.




Premium and Ultimate




Blue Net

Here you can burn a video file already created (mpg video), which you have saved on your hard disk, onto a CD/DVD.



Premium and Ultimate




Blue Net

Specify the relevant mpg file and what type of video is concerned.


SlideShow-Manager


In **AquaSoft® SlideShow Ultimate and Blue Net** you can also use **SlideShow-Manager** to burn your CDs/DVDs. It allows to burn multiple shows on one DVD and to create a DVD menu. If you're using **SlideShow Premium** and want to use **SlideShow-Manager** you can purchase it as a separate product.


You can open **SlideShow-Manager** from the **Wizards** menu.



Select a template for your DVD menu and adjust the individual settings for the menu. Under **DVD-Menu** specify aspect ration and video format.



By clicking the  button a dialog for burning the shows opens. Select **Video DVD**.



With **Burn project** you create a video DVD. Click **"Next"** and **"Export project"**.

You can find an extensive description of **SlideShow-Manager** in the help files of **SlideShow-Manager**. You can find it under "Help" in **SlideShow-Manager**.

5.2 PC-Show

Your slideshow can also be played back on a different PC, on which **AquaSoft® SlideShow** is not installed.

The **CD/Archiving Assistant** will assist you in burning your slideshows with all the data to a CD/DVD or archiving them on the hard disk.

Under **Wizards** you can open the **CD/DVD and Archive Wizard**.



After selecting the task, click **Next**.

Creating and burning a slideshow CD:



Specify a **title** for the CD/DVD. This title is used as the name of the CD/DVD.

Should you use fonts in the case of which you are not sure that they are installed on other PCs, you can also

burn them onto the CD/DVD.

Protect images from access:

Should you wish to pass on the CD/DVD, however not permit access to your images, you can have your images protected. This function is not suitable for archiving, since this show can no longer be edited. It can only be played back. It is no longer possible to restore the images. You should not delete your original images from the hard disk.

If you only want to create an ISO select the respective option. In this case the show will not be burned.

Click **Next** to start the selected process.

Archiving the slideshow, preparing the CD or passing on the slideshow

This option enables you to save all data (ads file, images, music) in a common directory. This option is also very well suited to archival storage. In this way the slideshow can also be saved on external data carriers (hard disks, USB sticks ...).



In order to save disk space, you can pack all the data into a ZIP archive.

If you use fonts in the case of which you are not sure that they are installed on other PCs, you can copy these as well.

You should copy the **Slideshow player** in order to be able to play back the show on computers on which **AquaSoft® SlideShow** is not installed. Without this player you cannot otherwise play back the show.


Click **Next** and then click **Start**. Now all necessary data for the show will be copied into the folder specified or combined into a ZIP archive.

5.3 Additional video formats

With **AquaSoft® SlideShow Premium** and **AquaSoft® SlideShow Ultimate and Blue Net** you can convert your shows into further video formats.

For that purpose, select the **User-defined video** option in the **Video Wizard**. In the dialog you can now select additional formats under **Video format**.

Check in advance with which codec videos have to be created, so that your DVD player plays them back (Operating Instructions). Then check whether this codec is installed on your PC. If not, you have to install the codec.



AVI-video

AVI is a widely used video format and will be played by newer DVD players.

Set the desired resolution and under **Compression**, you select the appropriate codec.

Please check first which codec has to be used for the creation of these AVI-videos so that your DVD-player will be able to play them (Operating instructions). Check to see if this codec is installed on your system. If not, you must install the codec. **AquaSoft @ SlideShow** doesn't provide any codecs.

In our [FAQ](#) you can find further informationen.



Please note that an AVI video should not be larger than 2 GB. Most players will **not** play a large AVI movie.

Not every codec supports all resolutions.

WMV-video

This format is only available in **AquaSoft @ SlideShow Ultimate and Blue Net**.

For the creation of a video in WMV format, you should install a recent version of Windows Media Player.

Using the WMV format, you can use a very high resolution for the video. The finished video can be played with Windows Media Player. Currently, only a few DVD players support this format.

5.4 Archiving a slideshow

Often you have invested a lot of time in a comprehensive and sophisticated show. As to not lose your work in case of a hardware crash you can save the complete show with all containing files (images, music, comments).

The **CD/DVD and Archive Wizard** offers you the opportunity to burn the complete show with all the data onto a CD/DVD or export it to an external drive.

This procedure is explained in the [PC Show](#) section.

5.5 Additional export options

There are other export option that you can read about in chapter [Export Wizard](#).

6 Image editing

6.1 Integrated image editing

It is our goal to provide you with all necessary tools in one single program, the **AquaSoft® SlideShow**. Therefore we integrated image editing functionality that allows you to enhance your photos for the slideshow. Of course there are specialized image editing applications that go far beyond the capabilities of the image editing module in **AquaSoft® SlideShow** but it should be possible to solve the most important tasks inside the program.



Use the right mouse button to click on the image and select the option **Edit image**. There are functions to crop and rotate images, for color correction, adjustment of brightness and contrast and some filters like blurring. By using the magnifying buttons (just like in [Layout Designer](#)) you can adjust the size of the display of the image or image segment.



None of the provided image editing functions modifies your original image.

The modification only affect the display of the images inside the slideshow.


6.2 AquaSoft® Image effects




The *Image effect editor* is only available in **AquaSoft® SlideShow Ultimate and Blue Net**.

With *Image effects* graphics can be optimized or spiced up. From a simple shadow over pleasing frames and collages to branched effect chains (Multiplicating) many things are possible. Complex effects are combined from different basic modules and allow non-destructive image editing (the original image always stays untouched).

When you click on an image in the *Image list* or *Timeline* you can select the menu item *Edit image*.




Under *Effects* the *Image effect editor* opens.



With the help of the *image effect editor* those effects can be assembled and saved to be reused later. Let's just start with a [shadow effect](#) and improve our skills to create a ["self-border"](#) afterwards.

6.2.1 A simple shadow


You need only a few clicks to assign an unobtrusive drop shadow to an image.



Sub-effects are simply added via the menu. Thus add the sub-effect **"Shadow"**.

Note: The number of available sub-effects in your version of the application can differ from that in the image above.

Now you can see that the shadow has been added to the previously empty **"effect list"**. On the right side of the dialog appear controls that let you adjust the settings of the shadow to your liking.



At the bottom-left the shadow effect is showcased on the butterfly graphic.

Each sub-effect can have very different settings. How each of them affects the result you can find out best by trial and error. In our specific example the offset of the shadow from the original image, the angle of the incidence of light, the strength of the blur and the transparency of the shadow can be specified.

That's all there is to it. Clicking **OK** applies the shadow to your image. Of course, all the settings can still be edited later. The original graphic is never changed.

6.2.2 A "self-border" using multiplication and transformation

We want to achieve an effect that used the image itself to create a semi-transparent border. The result will look similar to the picture below:




The basic idea of the solution looks like the following:

1. Enlarge the image and assign semi-transparency to it
2. Overlay the semi-transparent image with the original image

Here an important functionality is utilized that is also crucial for the creation of many other complex effects: Multiplication.

To achieve 2. at all a copy of the original image needs to be stored to be able to overlay the image that might already be changed by previously assigned sub-effects. The multiplication effect allows exactly this. By using it the normally flat list of effects will become a tree, because the multiplication effect can have child elements. The sub-effects can be moved around via drag&drop.

All effects that are children of the multiplication effect are "served" with that state of the image data source that has been current at the branching point, no matter in which way and how much a different child element has changed the image.



Here you see the completed effect: The multiplication effect got a transformation assigned as sub-effect that enlarges the image by a few millimeters. To that the transparency effect is assigned to make the image semi-transparent.

Now we need to use a little trick: To display the original image again we simply add a second transformation to the multiplication. Only this time no offset, rotation, etc. is set. So the image stays the same.


Note: Child elements of multiplication effects can have child elements themselves.

7 Wizards

7.1 Export Wizard

The **Export Wizard** will assist you in burning your finished slideshows onto a CD/DVD or archiving them, or also saving them as a video, to the hard disk.

You can access the **Export Wizard** via **Wizards -> Export Wizard**.




Burn onto CD/DVD

Select this menu item if you would like to record your show onto a CD/DVD.

PC/Data

Select this option if you would like to archive your slideshow and all associated data (images, music) on the hard disk or save it to the hard disk as a video.

If you would like to burn your show onto a CD/DVD, click **Burn CD/DVD** and then click **Open** (or double-click **CD/DVD**).



You now have several possibilities.

For the DVD player:**Video VCD**

Creates an MPEG 1 video and burns it onto a CD as a VCD.
Resolution: 352x288

Video SVCD

Creates an MPEG 2 video and burns it onto a CD as a SVCD.
Resolution: 480x576

Video DVD

Creates an MPEG 2 video and burns it onto a DVD as a video DVD.
Resolution: 720x576

Burn a video already created

Should you already have created the video, you can, in this way, burn the video onto a CD/DVD.
You can find out whether your DVD player plays back VCD and SVCD from the operating manual.

Note:


If you encounter difficulties replaying a burned VCD/SVCD/DVD on a DVD-player it can help to reduce the burning speed in the settings for the CD/DVD-burner and/or to change the brand of the CDs/DVDs.

You can find additional information in chapter [DVD-player](#).

For the PC:**Burn a PC-slideshow:**

With a PC slideshow, the images are not converted into a video. This CD/DVD can only be placed back on the PC (Windows 2000/XP/Vista). These CDs/DVDs are also well suited to archiving a show, since all pieces of music and images incorporated in the show are copied onto the CD/DVD.

Should you only wish to save your show on the PC, without burning it, you can open [PC/data](#) in the first step in the [Export Wizard](#).



Here you have the possibility of archiving/putting together the show for the PC or converting the show into a video. Additional information can be found in the [PC Show](#) section.

The grayed-out functions will become active only when you install [other products by AquaSoft](#) that come with

the respective plug-in.



The **Export Wizard** accesses the relevant wizard, according to the task selected. For output for DVD-player or for video creation it calls the **Video Wizard**. For output for PC it opens then **CD/DVD and Archiving Wizard**.

7.2 ScreenShow Wizard

Mit diesem Assistenten können Sie Ihre Show als Bildschirmschoner einrichten. Sie können auch einen Bildschirmschoner zum Weitergeben erzeugen.



Geben Sie in dem Feld **Titel** einen Namen für den Bildschirmschoner ein. Wenn Sie den Bildschirmschoner für Ihren PC erstellen, erscheint er unter dieser Bezeichnung in der Liste Ihrer installierten Bildschirmschoner. Wird der Bildschirmschoner jedoch als Weitergabe für andere PCs erstellt, stellt der Titel einen Teil des Dateinamens dar.



Weiterhin können Sie mit den Einstellungen das Abspielverhalten des Bildschirmschoners ändern. Entfernen Sie den Haken von **Sound verwenden**, wenn keine Sounds inklusive der Hintergrundmusik wiedergegeben werden sollen. Ist die Option **Bildschirmschoner an der letzten Position fortsetzen** markiert, dann beginnt

der Bildschirmschoner beim nächsten Start an der Stelle, wo er das letzte Mal beendet wurde. Wenn die Bilder nicht in der ursprünglichen Reihenfolge wiedergegeben werden sollen, können Sie die Abfolge der Bilder auf Wunsch durch Markieren der Option **Bilder in zufälliger Reihenfolge wiedergeben** per Zufall variieren. Mit der **Standardverweildauer** legen Sie das Zeitintervall fest, in dem ein Bild erscheint. Diese Option betrifft nur solche Bilder, welche die Standardverweildauer verwenden. Möchten Sie beim Bildschirmschoner den **DirectX-Player verwenden**, so können Sie die Option hier auswählen. Bitte beachten Sie dazu aber die Systemanforderung des Players. Für ältere PCs empfiehlt sich eventuell die Option zu deaktivieren.

Mit der Wahl des Ziels legen Sie fest, ob der Bildschirmschoner auf Ihrem PC installiert oder als Weitergabe für andere PCs erstellt werden soll.



Auf meinem PC verwenden

Wenn Sie sich für die 1. Option entscheiden, wird der Bildschirmschoner nach dem Erstellen sofort auf Ihrem PC eingerichtet. Sie müssen darauf achten, dass die Diashow weder gelöscht noch umbenannt wird, ansonsten kann der Bildschirmschoner nicht mehr korrekt ausgeführt werden.



Klicken Sie nun auf **Installieren**, um den Bildschirmschoner auf Ihrem PC einzurichten. Nach dem erfolgreichen Erstellen wird der Bildschirmschoner installiert und Sie erhalten ein Vorschau-Fenster, in dem Sie den Bildschirmschoner testen können.

Auf anderen Computern verwenden

Der ScreenShow-Assistent bietet Ihnen auch die Möglichkeit Bildschirmschoner als Weitergabe für andere

PCs zu erstellen. In diesem Fall wird der Bildschirmschoner nicht auf Ihrem PC installiert, sondern eine Datei mit der Endung **.scr** erzeugt. Hier ist Ihre Bilderliste bereits integriert, so dass Sie lediglich den Bildschirmschoner als einzige Datei weitergeben müssen.

Bevor der Bildschirmschoner erstellt werden kann, müssen Sie ein Zielverzeichnis auswählen, in dem der Bildschirmschoner gespeichert wird. Optional haben Sie die Möglichkeit die Datei zu komprimieren. Markieren Sie diese Option, wenn der Bildschirmschoner als Zip-Datei gespeichert werden soll. Auf Wunsch können Sie den erstellten Bildschirmschoner auch auf Ihrem System einrichten lassen. Aktivieren Sie dazu die Option **Bildschirmschoner auf meinem PC einrichten**. Die letzte Option ist jedoch nicht verfügbar, wenn der Bildschirmschoner komprimiert wird, da Windows keine gepackten Dateien als Bildschirmschoner verwenden kann.



Klicken Sie nun auf **Erstellen**, um den Bildschirmschoner zu erzeugen. Beim Erstellen wird die Bilderliste integriert und es genügt den Bildschirmschoner (als einzige Datei) an Ihre Freunde und Bekannte weiterzugeben.

7.3 SlideShow-Manager

The **SlideShow-Manager** allows to burn multiple shows to a CD/DVD. It creates a CD/DVD menu that allows to navigate to a certain show.

AquaSoft® SlideShow Ultimate and Blue Net already contains **SlideShow-Manager**. If you're using SlideShow Premium and want to use **SlideShow-Manager** you can purchase it as a separate product.

You can find an extensive description of **SlideShow-Manager** in the help files of **SlideShow-Manager**. A short description is included into this manual in chapter [DVD-Player](#).

7.4 Sound Wizard

Using the **Sound Wizard** you can record spoken commentaries and noises with your images using a microphone connected to the PC.


You will find the **Sound Wizard** in the menu under **Wizards**.




You can save the resulting files in the slideshow directory or in a separate directory.

Under **Record settings** you can decide the settings with which the commentaries should be recorded.


Then click **Next**.




Now all the images in the show with which you can include a commentary will be shown to you in sequence. To do so, simply click **Record** and then speak your commentary on the relevant image. Should you make a mistake while recording, you only need to re-record the commentary for the selected image.



With **Play** you can listen to your recording. In order to get to the next image, click **Next**. Once you have finished recording, close the Sound Wizard.

The **Sound Wizard** automatically matches up your images with the commentaries recorded. You can find the recorded file in the **Object settings** of the relevant image. The recording can also be played back here, using the  button.



The **Sound Wizard** can also be started directly from the **Object settings** of an image. For that there is the **Record** button.



The length of the image is automatically adapted to the length of the commentary.

7.5 Import Wizard

With this wizard you can import your images from a scanner or from your digital camera, as long as these devices respond to the [TWA IN32 interface](#). The images are saved and included in the [Image list](#). They can either be improved with the editing function immediately or later.

You can access these under [Wizards -> Import Wizard](#).



Specify a [Target directory](#) in which the images should be saved. Selected the desired file format and, if necessary, adjust the [Format options](#).

If the images are supposed to be directly included in the [Image list](#) of the slideshow, enable this function.

Then select the scanner or camera.

Next click [Next](#) and then click [Start](#). Your images are now imported.

7.6 PowerPoint Wizard

With the [PowerPoint Wizard](#) you can import your PowerPoint presentations into the slideshow. A prerequisite is that MS PowerPoint (Version 8 or later) is installed on your PC.

During import the individual slides are saved as images. All animations and effects will be lost in the process, however.


You can start these under [Wizards -> PowerPoint Wizard](#).

Specify the [File name](#) of the PowerPoint file to be imported.




Then click **Next**.

Specify a **Directory** in which the images should be saved. You can use the slide name as the file name or use the form **Imagexxx**.



Click **Next**.

Now you can set the image options. Select the desired resolution and the image format. Under **Format options** you can configure additional settings relating to the image format.



Click **Next** and then click **Import**. The slides are now converted into image files and inserted into your slideshow.

7.7 Video Wizard

In order to show your show on the television, you can create a CD/DVD for the DVD player with the **Video Wizard**. You can access this under **Wizards -> Video Wizard**.

An exact description of the wizard can be found in the [DVD Player](#) section.

7.8 CD/DVD- and Archiving Wizard

The **CD/DVD and Archiving Wizard** will be explained extensively in chapter [PC-Show](#).

7.9 Photo Frame Wizard

Using the Photo Frame Wizard you can transmit your slideshows as individual images or as a complete video on a digital photo frame.



Export as separate images

Firstly, specify the resolution of your frame. If you are not sure what resolution your device has, you will generally find details in the corresponding manual or on the manufacturer's web site.



Text can be included with your images, text animations will be dropped, though. The text becomes a static part of the image.

If your images have a different aspect ratio than your photo frame you can use the option Crop images to display them full frame.



In the last step select the storage location for your images. This can be the photo frame, a USB stick or a memory card.

Click **Start**. The wizard now computes your images in accordance with the predetermined settings and copies them into the target directory.



Transmitting a slide show as a video

If you want to transfer the whole show as a video please verify beforehand that your photo frame supports **Motion JPEG videos**.

This information should be provided in the manual of the photo frame.



In case your show has a different resolution than your photo frame you can now activate the option to correct the aspect ratio and fill the remaining borders with black. This way the images won't get distorted. You can also decide to integrate sound and music into the video, which only makes sense if your photo frame is able to replay them.



In the last step select the storage location for the video. This can be the photo frame, a USB stick or a memory card.

7.10 PSP Wizard

To transfer the slideshow to your Playstation Portable please follow the next steps.

Connect the PSP to your PC


Use the USB cable that came with your PSP to connect it with your computer. In the menu of the PSP go to the Settings menu and select the entry **USB connection** using the arrow keys, and then hit press the X key of the PSP. As soon as **USB mode** is displayed the PSP is connected to your computer.

Start the PSP-Video-Wizard

If you haven't done yet please open the slideshow you want to transfer with AquaSoft® SlideShow. Then select the menu item **Wizards -> PSP Wizard** to open the dialog for the transfer to your Playstation Portable.



As long as the PSP is not correctly connected to your computer this state is displayed



On the first page of the wizard you have the option to choose from different resolutions. Since the display of the PSP has a 16:9 format you can choose this option to create screen-filling videos. Limit the size of the video if your PSP doesn't have enough memory available. The smaller the file size of the video the lower the video quality will be.

Then click **Next** to reach the next page of the wizard.

Specify the title of the video and a preview image

Provide a meaningful title for your video on the next page so that it can be found quickly. It will appear, together with the preview image, on the video list of your Playstation Portable after the transfer.



You're done

Please wait while the slideshow for your PSP is being created. Depending on its size this process can take several minutes. Afterwards the video will be transferred to your PSP at once. Now present your slideshow - whenever, where ever.



If your PSP is not connected to your PC you can store the video file after its creation on your computer. So you can transfer the video yourself to your PSP at a later time.

7.11 iPod Wizard

To transfer the slideshow to your Apple iPod please follow the next steps.

Connect the iPod to your PC

Use the USB cable that came with your iPod to connect it with your computer. As soon as the message **"Don't disconnect"** appears the iPod is connected with your computer. In addition you need to install the software iTunes on your PC to be able to transfer the video. If you haven't done so already please download this free software from this Internet address <http://www.apple.com/itunes/download/> .

Start the iPod-Video-Wizard

If you haven't done yet please open the slideshow you want to transfer with AquaSoft © SlideShow. Then select the menu item **Wizards -> iPod Wizard** to open the dialog for the transfer to your iPod.



U

As long as the iPod is not correctly connected to your computer this state is displayed



On the first page of the wizard you have the option to choose between the default 4:3 or a user-defined resolution. Limit the size of the video if your iPod doesn't have enough memory available. The smaller the file size of the video the lower the video quality will be.

Then click **Next** to reach the next page of the wizard.

Specify the title of the video

Provide a meaningful title for your video on the next page so that it can be found quickly. It will appear on the video list of your iPod after the transfer.



You're done

Please wait while the slideshow for your iPod is being created. Depending on its size this process can take

several minutes. Afterwards the video will be transferred to your iPod at once. Now present your slideshow - whenever, where ever.




If your iPod is not connected to your PC you can store the video file after its creation on your computer. So you can transfer the video yourself to your iPod at a later time.

7.12 Mobile Wizard

To transfer the slideshow to your mobile phone or PDA please follow the next steps.

Configuring your Bluetooth device on your PC

If you want to connect your device via Bluetooth with your computer you have to configure the mobile device on your PC once. To do that go to **Windows Start menu** and click **Control Panel -> Bluetooth Devices**. Now the Bluetooth Device Dialog appears. Press **Add Wireless Device...** to execute the Bluetooth Wizard. After a successful configuration your device is ready for Bluetooth transfer.





If you connect your mobile device via Infrared or cable you can skip this step.

Start the Mobile Wizard

If you haven't done yet please open the slideshow you want to transfer with AquaSoft® SlideShow. Then select the menu item **Wizards -> Mobile Wizard** to open the dialog for the transfer to your mobile device. Select the radio button **Use current slideshow for my mobile device** to transfer the current slideshow.



Select your device

On the following page you select the target device. You can create videos for your mobile phone or your PDA. If you cannot find a suitable profile you can configure the settings manually. Then click **Next** to create the video.



Before you change the settings manually please consult the user manual for your device to learn which video options your device supports. Important are especially the video resolution, as well as the supported video formats. Experiment a little with the settings to find the best possible configuration. Typical video resolutions for mobile phones are 176x144 pixels and 128x96 pixels.

Specify the title of the video

Provide a meaningful title for your video on the next page so that it can be found quickly. It will appear on the video list of your mobile device after the transfer.



Transfer the video to your mobile device

The video is now ready to be transferred to your mobile device. You have the option to transfer it via Bluetooth, Infrared or USB cable. Please create a connection to your phone or PDA. Click [Search for devices](#) to determine all devices connected to your PC.



Wireless transfer via Bluetooth/Infrared

You need a Bluetooth/Infrared receiver in your PC for wireless transfer. These interfaces are mostly in place in modern Notebooks, but if they aren't you can upgrade your computer for only a little money. Usually these devices are offered as small USB sticks.

Follow these steps to transfer the video to your mobile device wirelessly:

1. Activate Bluetooth or Infrared on your mobile device as well as on your PC. When using Bluetooth you have to register your device on your PC once (see first paragraph of this chapter)

2. If the devices are in close enough distance to each other the connection will be created automatically. If you're using Infrared the emitters need to "see" each other. With Bluetooth it is sufficient for your mobile phone/PDA to be in the same room as your PC.
3. Your device should appear in the list of detected devices. If you start the video transfer via the wizard you'll to accept the video file on your mobile device to allow the transfer.
4. After the transfer was successful the video is located on your mobile phone/PDA and you can replay it.

Transfer via USB cable

Prerequisite for a transfer via USB cable is the recognition of your device as removable medium. Please consult the user manual of the device to see if this feature is supported.

1. Connect your device to the PC using the USB cable.
2. The device should now be recognized as removable medium.
3. In the Mobile Wizard select the option **Save to disk**.
4. As target drive you select the drive letter that has been assigned to your device. Possibly you have to save the video to a certain folder. Please consult the user manual of your device.

Transfer using the software of your mobile device

A transfer of the video by using the software provided with your mobile phone/PDA is to be taken into consideration if you cannot transfer it wireless nor via USB cable with the wizard. At first save the video with the option **Save to disk**. Then launch your mobile phone/PDA software to transfer the newly created video to your device.



Not every mobile device can replay all video formats. The user manual of your device usually lists the supported formats. If you encounter difficulties replaying the video your device doesn't support its format. In this case use a different profile for the video creation and transfer the video once more.

If the transfer with the wizard doesn't work please use the transfer software that came with your device. In any case: Please consult the user manual of your mobile device. Every mobile phone/PDA is different and needs to be handled differently.


You're done

The video is now stored on your mobile device. In the last step of the wizard you have option to transfer the video to a different device or to save it to your hard drive. Select the option **End wizard** to finalize the process.



7.13 Find missing files

AquaSoft ® SlideShow only saves links to your images and music which you use in the slideshow. Should you move, delete or rename your images. **AquaSoft ® SlideShow** can no longer access them. You will then see the following notice in the *Layout Designer*.



AquaSoft ® SlideShow cannot retrieve/recover deleted images.

Under *Wizards -> Find files* you can call the *Search Path Wizard*.



Here you have several search possibilities.

If you are not sure where the files sought are located now, activate the automatic search.


If you know exactly in which directory your images are located, you can also directly specify the path.

If you want to convert the path from absolute (details of paths are saved in their entirety) to relative (details of paths are saved in relation to the location of the ADS file) or vice versa, select the relevant option.


Then specify the entries that should be adapted.

Click **Next**.

Now select where your images should be sought.



Click **Next** and the search starts. Afterwards the results of the search are shown to you.




Click **Finish** and your slideshow is updated.

8 Variables


In **AquaSoft® SlideShow** there is the possibility of having certain image information displayed as a text in the image, e.g. the date taken, the file name or the path to the image. This occurs by means of **Variables**.

These have to be specified in the format below in the **Text** field in the **Object settings** of an image:



In principle, **Variables** have to be enclosed between two % signs.


In the **Layout Designer** you will then see the implementation of the **Variables**.




EXIF information on your images can also be included using **Variables**. In that respect, your image must contain **EXIF data**.

You can check this by clicking on an image and then having the *meta-data* displayed under *View -> Controls*. Should these be empty, your image does not contain this data.

You will find a *list* of all possible *Variables* in the program under *Tools -> Program settings -> Plug-ins*.



After clicking the *Info about plug-ins* button a window is opened, in which the *Variables* are listed.



You have to scroll down a bit in order to get to the list with the *Variables*.

9 Settings

9.1 View settings

In SlideShow you can choose from different pre-defined views on the main toolbar and under **View**. If you want to add other modules to the current view you can select from the menu under **View -> Controls**.

Please have a look at our screencast to learn how to create your own favorite layout. The screencast is available at the following web address:

http://aquasoft.de/download/flash/edit_view_cast/ansicht_editieren.html

In **AquaSoft® SlideShow Ultimate and Blue Net** you can save your layouts under **View -> View management**.


9.2 Slideshow settings

The slideshow settings can be individually changed for each slideshow.

Under **Slideshow -> Settings** you can access the window for the **Slideshow settings**. You can also access

the settings directly via the  button in the menu bar.

Basic settings:



Here you can change the **Standard exposure time** of your images, as well as select a **Random playback sequence** for your images.

You can adjust the "display quality" according to the performance of your computer here. The higher the quality the higher is the required performance. This setting is of no importance during the creation of the video. It concerns the quality when replaying the show using the **AquaSoft® SlideShow Player**. If the "display quality" is too high for your PC this can lead to a jerky replay experience of your show.

You can likewise set the **Aspect ratio** of your show here. Should this not correspond to the aspect ratio of your

images, you will get edges or you fit your images into the desired aspect ratio.


Under **SlideShow Player** you can choose between the **Software Player** and the **Standard Player (DirectX)**. For the **Standard Player (DirectX)** a DirectX 9c-compatible graphics card with at least 64 MB memory is required. It is also mandatory that you use the manufacturer's current graphics card driver!

If you still have an older graphics card or one with little memory please use the **Software Player**. If your show is set to use the **Standard Player (DirectX)** it will be checked if it is possible to use it with your graphics card before playing the show. If this isn't the case the **Software Player** is used automatically.

The **Standard Player (DirectX)** is considerably more powerful than the **Software Player**, however a corresponding graphics card is required.


You will find settings for the corresponding **SlideShow Player** further on in this section.

Slideshow flow:




Here you can change the **Default duration** of your images, as well as select to **Play images in random order**.

Slideshow end:



Here you can decide what is supposed to happen at the end of the slideshow played back. Do you want the show repeat itself or stop after the first run? You can also let the viewer decide.

Transitions:



Here you can select which transitions are supposed to be included in the **Random transition**. All those with green check marks are included, all those with a red cross are not included.


Music settings:

The music settings are explained in further detail [here](#).

Background music:


The topic of background music is dealt with in detail [here](#).

Description:




You can individually personalize your show. Here you can specify a title, author and a description of your show.

Logo:



If you want to start your show with a **Logo** you can select and image here. You can also simply omit a logo.

Standard player:



The **AquaSoft SlideShow Player** takes on the task of playing back a slideshow. Here you can decide the settings for it. First check which **SlideShow Player** you are using. You will see this in the **Basic settings**.

Select here if you want the show to be replayed in full screen or window mode.

Use the settings for **Antialiasing** to remove ugly artefacts at the edges. The best way to recognize the difference is by rotating a black square in front of a white background and closely watching the edges. If the option is set to **Automatic** the level with the highest possible quality will be used. The other option cause 2x, 4x, 8x, 16x oversampling of the image, with correspondingly increasing effort. This requires a lot of computing power of the graphics board and can lead to jerkiness at high resolutions and older and cheaper boards. Nonetheless, the gain of quality is, depending on the displayed contents, remarkable. Older graphic boards should be used with the option **None**.

You can also specify the setting for the **Navigation bar**, i.e., how and when you want it to be displayed.


Under **Control** you can select if you want the show to be started automatically after clicking Play or if you want it to wait for an input, i.e., if you want **manually control** your show. You can also activate the option to control the image change with the mouse.

The **IntelliLoad** specifies how many seconds of the show should be loaded in advance.


If you want to use the selected settings as default for every new slideshow then click **As default**. These settings will then be automatically assigned to all future shows. By clicking the button **Original settings** you can reset all settings to the factory values.

9.3 Music settings

You can reach the music settings via **Slideshow -> Settings -> Music settings**.




The **Music settings** can be set as desired for each show. The standard settings are illustrated.



You decide here whether background music is supposed to be included in your slideshow or not.




In the **Background music** menu you can insert several tracks to provide background music for your show. Here you can decide whether this list should be repeated if all tracks have been played and the slideshow has not yet come to an end.



Via this button you can access the **Background music** menu and can remove or insert tracks there.




Here you can set at what volume the tracks should be played back (100% = full volume).



Here you can specify the length of the fading out.



The background music can be gently faded out towards the end of the slideshow or simply broken off.



If you use **Sound** objects or have recorded commentaries for your images in your show, it is expedient to fade out the background music when playing back these objects. Specify here to what volume the sound should be faded out.

0% = Fade out completely

100% = Do not fade

Fade duration: 0.30 sec

Determines over what period of time the music should be faded.

Fade sounds too

Here you can specify whether the background music should also be faded with included **Sound** objects.

Synchronize background music with slide show


If you use breaks and continue manually during the show, you can decide whether the music should also be interrupted during an image break, or whether it should continue. If a check mark is placed, the music stops during a break.

9.4 Program settings

The **Program settings** refer to the basic settings of the program and not to the individual settings for your slideshow. For the slideshow created by you, the **slideshow settings** are decisive.


Under **Extras -> Program settings** you can access the program settings.

Plugins:




Contains a list of all plug-ins additionally installed which have been installed by additional **AquaSoft** applications.

Add files:




Here you can determine how files are supposed to be inserted into a slideshow and how they should be arranged in this slideshow.

User interface:




Here you will find additional setting options for the user interface of **AquaSoft® SlideShow**.

Temporary directory:




AquaSoft ® SlideShow from time to time requires temporary disk space on the hard disk. Here you can specify in which directory temporary files may be buffered. A lot of memory is necessary during video creation. If the Temp directory doesn't provide enough space you can specify another directory here.

Language:




AquaSoft ® SlideShow supports several languages, which you can change here.

Automatic update:




Here you can set the intervals at which **AquaSoft® SlideShow** is supposed to check for updates. This way you stay up to date. So bleiben Sie immer auf dem aktuellsten Stand. Zur Prüfung wird eine Verbindung zum Internet benötigt.

Record sound:




Using the **Sound Wizard** you can record spoken commentaries with your images by means of a microphone connected to your PC. Configure the recording settings here.

Sound system:




The **Sound system** takes on the task of playing back the music included in the slideshow. Should you have irregularities when playing back the music, set the setting to **Windows Multimedia** here and then restart **AquaSoft® SlideShow**.

CD/DVD writer:




Here the recognized CD/DVD writers are shown.

Confirmation:




Select the dialogs to be shown here.

Automatic saving:




Here you can determine whether backup copies should automatically be generated while you are working on a slideshow. Under **File -> Open -> Restore** you can access an earlier status of your work.

Storyboard:




Configure your settings for the [Storyboard](#).

Layout Designer:




You can configure settings for the [Layout Designer](#) here.

Timeline:



Configure the settings of the *Timeline* here.

Image list:



Here you can select which information should be displayed in the *Image list*.

10 Technical information

10.1 Common preparations

Directories

In order to achieve a good result quickly and effectively, you can make some minor preparations in advance. **AquaSoft ® SlideShow** saves an image list and, in that respect, keeps an eye on all directories specified.

Image format

AquaSoft ® SlideShow supports, inter alia, the following image formats.



As background sound the following file formats may be used:



Please note that MID and RMI files cannot be used when creating the video with the Video Wizard.



Only use unencrypted music tracks for your slideshows. For legal reasons, **AquaSoft® SlideShow** does **not** support the use of music tracks which have been encrypted by DRM or similar procedures.

10.2 Installation

To install **AquaSoft® SlideShow** we suggest at least the following system setup. More resources will lead to higher quality playback:

Hardware

CPU - 1 GHz

Graphics board - DirectX 9c-compatible graphics board with 64 MB RAM for use of the DirectX-player. For older graphics boards the Software-Player is available to play slideshows.

RAM - 512 MB

Harddrive - 150 MB (burning (S)Video-CDs may need space up to 1,2 GB for a short time, burning Video-DVDs may take up to 10 GB temporarily)

CD/DVD-burner - (optional)

Operating system

Windows XP Home and Professional, Vista, Windows 7

not supported are the operating systems:

DOS, Windows 3.x, Windows 95, 98, ME, 2000, Unix, Linux, Apple Macintosh, Novell, etc.

10.3 Full screen mode with different screen resolution

You can modify the graphic mode for the full screen display in the player settings. When switching the screen resolution Windows can only assign a fixed or no frame rate at all. Since we can't know your graphics card/monitor combination we omitted the assignment of a fixed frame rate. This was done to prevent any danger for your monitor. Windows automatically switches to one of the possible modes, which you can change yourself. (see Control panel -> Display -> Settings)

This hint is only of interest if you want to work with a modified full screen mode. The problem does not exist in window mode.

11 Ordering AquaSoft® SlideShow


The easiest way to order a product by AquaSoft is to visit our [Online Shop](#). Here you can always find the newest offers and also bundles (combinations of several products), which you can save a lot of money with. In addition you'll receive the newest updates.

12 Other programs by AquaSoft

AquaSoft SlideShow is just one of many useful programs created by AquaSoft. On the following pages you can find additional programs with interesting features and useful enhancements.

12.1 AquaSoft® Barbecue

The new image processing software **AquaSoft® Barbecue**



The new image processing and managing software **AquaSoft® Barbecue** is photo studio as well as image factory. With just a few clicks you design your images yourself. The new built-in undo functionality makes mistakes practically impossible. Macros are being created using the mouse - as easy as never before. All steps in the process can be saved and are reusable for an unlimited amount of images. **AquaSoft® Barbecue** takes into consideration the development of digital photography. Therefore we integrated JPEG-2000 and the reading and writing of EXIF data. Thus **AquaSoft® Barbecue** becomes a must for all owners of digital cameras. An extensive manual in PDF format is waiting for you, as well.

Some features:

- changing resolution and formats
- evaluating EXIF data and their use as renaming information
- static integration of water marks, stamps, logos, texts and own drawings into the image
- zoom functionality
- extensive image editing program

For instance you can convert hundreds of blue-cast, to dark 640x480 BMP images into colour corrected 320x200 JPEG images, for which you can set the compression rate, that are fit for the Internet. Especially the integration of image editing, file conversion, the writing of JPEG2000 and Lurawave into an automated batch conversion makes it a program that the community has been waiting for for a long time. In short, **AquaSoft® Barbecue** is a batch-image-converter with image editing functionality.

More information on the Internet: www.barbecue.aquasoft.de

12.2 AquaSoft® DiscMenu

AquaSoft® DiscMenu - Your professional CD-ROM-Publishing-System



You have the best contents but nobody looks at them? Endless amounts of data can be stored on CDs or DVDs. But it needs a lot of care to make these data accessible to the user. What if you could organize the contents of your CD through easily to create HTML-pages? Great idea! What's missing now is a suitable environment because a normal web browser for displaying the page neither looks professional nor does it provide the opportunities to customize its look. On top of that there are quite a few obstacles to overcome. Good that there is **AquaSoft® DiscMenu**.

The start menu for your CD or DVD:

- the auto-start menu for your installation file and other applications
- the business card of your company with navigation
- your product presentation on CD or DVD as advertisement
- the information system for your documentation
- a new way for your multi-media application

You want to distribute eLearning-products or start eBooks, audio books, movie or sound files from CD?

AquaSoft® DiscMenu provides the features of a multi-media authoring system!

More information on the Internet: www.aquasoft.net

12.3 AquaSoft® Multimediawerkstatt

Multimediawerkstatt - digital learning - a child's play



AquaSoft® Multimediawerkstatt is a software for playfully learning the use of computers and media. Designed for children in grade school **Multimediawerkstatt** is an open creativity platform that combines painting, writing, voice recording and presenting in one program.

Intuition and esprit - childlike fantasy burnt on CD

Due to its intuitive comprehensibility **Multimediawerkstatt** is particularly suited for young students and users without any computer experience. Almost in no time adventures are cast in digital format, and different sources are connected to self-running presentations. Just like a slide show are the stories of our children replayed on computer or burnt on an auto-starting CD. A multimedia software with esprit for school and leisure time.

More information on the Internet: www.aquasoft.net

12.4 AquaSoft® PhotoAlbum

AquaSoft® PhotoAlbum - Get more out of your photographs



Digital photos are great but they aren't everything. You will come to a point where you wish you could look at them in print. That's way you can say, paper photographs are alive and well.

With **AquaSoft® PhotoAlbum** you can offer more than just lose photos to the admirers of your artwork. No boring albums but exciting effects give your pictures center stage. Whether you want to spice up your desktop, produce creative photo books or wake up your printer from its hibernation is up to you. In **AquaSoft® PhotoAlbum** everyone finds what is needed.

And these are the three easy steps:

- adding images
- selecting a template
- creating the photo album

AquaSoft® PhotoAlbum already comes with many prepared templates. But with the integrated template editor you can design your album to the smallest details yourself, as well. There are no limits. Title pages, chapters, thumbnail view (contact print) and much more can be designed and positioned. Create professional photo books just as easy as funny ones, e.g. with pictures that seem like pasted in.

Enough of always the same desktop wallpaper? With the integrated Desktop-Album you can revive the memories of your last holidays. It's not just a simple one-after-the-other of your photos but they are professionally embedded in an interesting environment.

More information on the Internet: www.aquasoft.net

12.5 AquaSoft® PhotoCalendar

AquaSoft® PhotoCalendar - Your photos, around the year.



There's always a time to give gifts. So, what's more suitable than to give a calendar, then?

AquaSoft® PhotoCalendar is a universal program for the creation of customized calendars. Ready-made templates ensure the desired result with just a few clicks.

And these are the three easy steps:

- adding images
- selecting a template
- creating the photo calendar

AquaSoft® PhotoCalendar already comes with many prepared templates. Calendars for printing or your desktop, for giving away or keeping. Cover pages, any number of pictures per page, appointment books, weekly, monthly, yearly calendars, etc. - leave room for your creativity. Create new calendar layouts to the smallest detail with the help of the integrated template editor. Whether simple, advanced, funny or formal - everything can be achieved in a professional manner.

Specify birthdays and appointments. Every event will be displayed with photos on the correct day. PhotoCalendar also imports your appointments and birthday list from MS Outlook.

The DesktopCalendar brings your photos as a photo calendar to your desktop, including your specified events. This too includes your MS Outlook events.

More information on the Internet: www.aquasoft.net

12.6 AquaSoft® ScreenShow

AquaSoft® ScreenShow - Take a break and enjoy your pictures.



People always have been charmed by moving pictures. Put the magic of your photos on your screen. With **AquaSoft® ScreenShow** you can create your own photo screen savers with impressive transitions and background music. And it can be done with just a few mouse-clicks. You can use these screen savers on your own PC or you can distribute them, e.g. per eMail.

And these are the three easy steps:

- adding images
- entering a title
- creating the screen saver

More information on the Internet: www.aquasoft.net

12.7 AquaSoft® WebShow

AquaSoft® WebShow - Waltzing from a photo to a website



While the Vienna Waltz uses three steps converts the program **AquaSoft® WebShow** your photos into a ready-to-go website. That's right! In just three steps a complete website is created including picture frames, background, thumbnail navigation and, if you wish, transition effects.

And these are the three easy steps:

:

- adding images
- selecting a template
- launch the website

Whether for family or for presentations in the company, for you it is important to embed your photos and pictures into a pleasing Internet site with just a few clicks. From the abundance of web templates you can create a professional web project with overview page (thumbnails), navigation buttons and comments.

And those who want can dance the foxtrot. Then there is a fourth step available for setting the page properties where all possible configuration can be made. E.g. you choose a picture frame, a certain background color, a button style - even whole themes are available. Due to the powerful, XML-based scripting language of the templates you can create your very own templates, as well. There are virtually no limits: you can use everything that is supported bei HTML, PHP, ASP, Javascript etc. Again, you can but you don't have to. Because **AquaSoft® WebShow** has almost everything prepared for you.

More information on the Internet: www.aquasoft.net

13 AquaSoft ®

13.1 If you have problems

The AquaSoft-homepage offers software on the topics of education, image editing and image management as well as further shareware and freeware for download.

Visit our homepage at www.aquasoft.net. You will find downloads, FAQ, forums and information on our products.

If you have trouble with an AquaSoft product or questions, criticism, praise, please proceed as follows:

- Check the manual or the according help file.
- Try finding an answer in the FAQ (Frequently Asked Questions).
- Visit the respective forum. There users can exchange experiences and can ask questions. Write your own entry. Sometimes it is easier for another user to understand the question than for a whole team of developers - and the answer might come quicker, too.
- Only after those steps didn't succeed, write or call us. We take your suggestions as important help, but we also need time to advance the software.
- The contact email address is: info@aquasoft.de

AquaSoft SlideShow - Help

Copyright © AquaSoft GmbH 1999-2015

Visit us on the Internet:
www.aquasoft.net

